



Installation and Configuration Guide

VERSION 2016.0.02

jade

Jade Software Corporation Limited cannot accept any financial or other responsibilities that may be the result of your use of this information or software material, including direct, indirect, special or consequential damages, or loss of profits. There are no warranties extended or granted by this document or software material.

You should be very careful to ensure that the use of this software material and/or information complies with the laws, rules, and regulations of the jurisdictions with respect to which it is used. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of Jade Software Corporation Limited.

The information contained herein is subject to change without notice. Revisions may be issued to advise of such changes and/or additions.

Copyright © 2018 Jade Software Corporation Limited.

All rights reserved.

JADE is a trademark of Jade Software Corporation Limited. All trade names referenced are the service mark, trademark, or registered trademark of the respective manufacturer.

For details about other licensing agreements for third-party products, you must read the JADE **ReadMe.txt** file.

Contents

Contents	iii
Before You Begin	vii
Who Should Read this Guide	vii
What's Included in this Guide	vii
Conventions	vii
Related Documentation	viii
Chapter 1 Installing JADE under Windows	9
Operational Requirements	9
Hardware Requirements	9
Minimum Hardware Requirements for a JADE Database Server	10
Processors	10
Memory	10
Storage	10
Other	10
Minimum Hardware Requirements for an Application Server	11
Processors	11
Memory	11
Storage	11
Other	11
Minimum Hardware Requirements for Standard Clients	11
Processors	11
Memory	11
Storage	12
Other	12
Minimum Hardware Requirements for Running Presentation Clients	12
Processors	12
Memory	12
Storage	12
Other	12
Software Requirements	12
Additional Software Requirements for Deploying JADE Web Applications	13
ODBC Requirements for External Database Coexistence or JADE ODBC Driver Usage	13
JADE Generic Messaging Requirements	14
.NET Requirements	14
Requirement for Postscript Printing	14
Requirements for RPS Nodes	14
Virtual Environments	15
Installing Your JADE Software	15
Initiating the Installation from the JADE Setup Program	15
JADE Software Installation Process	15
Displaying the Welcome Dialog	16
Accepting the Terms of the JADE License Agreement	16
Selecting the Type of Installation	16
Selecting the Type of Set Up	16
Selecting the Components to Install	16
Specifying Your User Information	17
Selecting the Destination Directory	17
Selecting the Program Folder for the JADE Icons	18
Running the Installation Program	18
Informing You When the Installation is Complete	18
JADE Configurations under Windows	18
Multiuser Configuration	19
Running a JADE Server in Multiuser Mode	19
Running a JADE Client in Multiuser Mode	19
Running a JADE User Application in Multiuser Mode	20
Running an Application Server in JADE Thin Client Mode	20

Running a Presentation Client in JADE Thin Client Mode	20
Single User Configuration	21
Running JADE in Single User Mode	21
Running a JADE User Application in Single User Mode	21
Installing Multiple JADE Initialization Files	21
Reregistering JADE with a New Licence	22
Chapter 2 Configuring JADE	25
Example Production System Configurations	26
Directory Locations	27
Installation Directory Location	27
Home Directory Location	27
Program Data Directory Location	28
User Data Directory Location	28
Work File Directory Location	29
Configuring Your Network Protocol	30
Selecting Network Addresses	30
TCP/IP Transport	31
Hybrid Pipe Shared Memory (HPSM) Transport	32
JadeLocal Transport	33
Format of the Server URI String	34
File Scheme (Single User)	34
TcpIP, TcpIPv4, and TcpIPv6 Schemes	34
Hybrid Pipe Shared Memory (HPSM) Scheme	35
JadeLocal Scheme (Shared Memory)	35
Server Thread Model	36
Connecting to JADE Applications from Internet Information Server (IIS)	36
Connecting to JADE Applications from an Apache HTTP Server	37
Using the mod_jadehttp Module	38
Configuring Your JADE Software	38
Configuring the Internet Protocol Version	39
RPC, Database, and Node Configuration	40
Configuring the Database Server	40
Configuring the Client Node	40
Configuring SDS Connections	41
Application Server and Thin Client Configuration	41
Configuring the Application Server	41
Configuring a Presentation Client	42
TcpIpConnection Class	42
Other User Networking Areas	42
Limits and Defaults	43
Configuring JadeHttp for Remote Connections	43
Firewall for the JADE Internet Environment	44
Files Created by the JADE Application	44
Files Transferred from the Web Browser	46
Internal Housekeeping of the Virtual Directory	47
Controlling the Location of Files Uploaded via a Web Application	47
[application-name] Section	48
ApplicationType	48
CloseDelay[n]	49
ConnectionGroup[n]	49
MaxInUse[n]	49
MaxMessageSize	50
MessageTimeout	50
MinInUse[n]	50
MinMessageSize	51
PurgeDirectoryRule	51
PurgeFileAge	51
TcpConnection[n]	52
TcpPort[n]	52

VirtualDirectory	52
Sample [application-name] Section	52
[Jadehttp Files] Section	53
FileTransferDirectory	54
Firewall	54
Sample [Jadehttp Files] Section	55
[Jadehttp Logging] Section	55
Trace	55
TraceFile	55
Sample [Jadehttp Logging] Section	56
Configuring Apache for Remote Connections	56
Apache Configuration Directives	56
SetHandler	57
ApplicationType	58
Application	59
FaultDocument	59
FileTransferDirectory	60
Firewall	60
JadeHttp_Trace	61
JadeServer	62
JadeTimeout	63
LocalInterface	63
MaxMessageSize	64
MinMessageSize	65
PhysicalDirectory	65
PurgeDirectoryFrequency	66
PurgeDirectoryRule	66
PurgeFileAge	67
TcpConnection[n]	67
MinInUse	68
MaxInUse	68
CloseDelay	68
ConnectionGroup	68
VirtualDirectory	69
Apache Configuration Examples	69
Minimal Configuration Example	70
Extended Configuration Example	70
Extended Configuration Example with Additional Apache Directives	71
Apache Considerations	72
Tuning Your Systems	73
Specifying Parameters in the JADE Command Line	73
Placing Initialization File Parameters on the Command Line	77
Handling Multiple Copies of the JADE Program	78
Specifying Your Administration Options	78
Using the File Menu	79
Saving Your Options and Logging Off	80
Logging Off from the Installation Preferences Dialog	80
Saving Options and Exiting from the Installation Preferences Dialog	80
Exiting from the Installation Preferences Dialog	80
Using the Admin Menu	80
Resetting JADE Default Preferences	81
Removing Source Code	81
Backing Up Your Development Database from a Client Workstation	81
Using the Patch Menu	82
Using the Help Menu	82
Specifying Your JADE Installation Preferences	82
Maintaining Painter Options	84
Reregistering a JADE System in Batch Mode	85
path	85
ini	85
name	86

key	86
online	86
minStandard	86
minJade	86
report	87
help	87
Using the JADE Version Information Utility	87
Checking which Hot Fixes are Applied	89
Obtaining the Version Number of User Database Files	89
Using the JADE Sentinel Process Dumps Program	90
Appendix A Exit Values	91
Overview	91
Enabling the Use of Generic Exit Values for Windows	91
General Exit Values Unique to Each Program	92

Before You Begin

The *JADE Installation and Configuration Guide* is intended as the main source of information when you are installing and configuring JADE.

Who Should Read this Guide

The main audience for the *JADE Installation and Configuration Guide* is expected to be system administrators.

What's Included in this Guide

The *JADE Installation and Configuration Guide* has two chapters and one appendix.

Chapter 1	Covers installing JADE
Chapter 2	Covers configuring JADE
Appendix A	Covers the JADE program and warning exit values

Conventions

The *JADE Installation and Configuration Guide* uses consistent typographic conventions throughout.

Convention	Description
Arrow bullet (➤)	Step-by-step procedures. You can complete procedural instructions by using either the mouse or the keyboard.
Bold	Items that must be typed exactly as shown. For example, if instructed to type foreach , type all the bold characters exactly as they are printed. File, class, primitive type, method, and property names, menu commands, and dialog controls are also shown in bold type, as well as literal values stored, tested for, and sent by JADE instructions.
<i>Italic</i>	Parameter values or placeholders for information that must be provided; for example, if instructed to enter <i>class-name</i> , type the actual name of the class instead of the word or words shown in italic type. Italic type also signals a new term. An explanation accompanies the italicized type. Document titles and status and error messages are also shown in italic type.
Blue text	Enables you to click anywhere on the cross-reference text (the cursor symbol changes from an open hand to a hand with the index finger extended) to take you straight to that topic. For example, click on the " Work File Directory Location " cross-reference to display that topic.
Bracket symbols ([])	Indicate optional items.
Vertical bar ()	Separates alternative items.
Monospaced font	Syntax, code examples, and error and status message text.
ALL CAPITALS	Directory names, commands, and acronyms.
SMALL CAPITALS	Keyboard keys.

Key combinations and key sequences appear as follows.

Convention	Description
KEY1+KEY2	Press and hold down the first key and then press the second key. For example, "press Shift+F2" means to press and hold down the Shift key and press the F2 key. Then release both keys.
KEY1,KEY2	Press and release the first key, then press and release the second key. For example, "press Alt+F,X" means to hold down the Alt key, press the F key, and then release both keys before pressing and releasing the X key.

Related Documentation

Other documents that are referred to in this guide, or that may be helpful, are listed in the following table, with an indication of the JADE operation or tasks to which they relate.

Title	Related to...
JADE Database Administration Guide	Administering JADE databases
JADE Development Environment Administration Guide	Administering JADE development environments
JADE Development Environment User's Guide	Using the JADE development environment
JADE Developer's Reference	Developing or maintaining JADE applications
JADE Encyclopaedia of Classes	System classes (Volumes 1 and 2), Window classes (Volume 3)
JADE Encyclopaedia of Primitive Types	Primitive types and global constants
JADE External interface Developer's Reference	Developing JADE applications using external interfaces
JADE Initialization File Reference	Maintaining JADE initialization file parameter values
JADE Synchronized Database Service (SDS) Administration Guide	Administering JADE Synchronized Database Services (SDS), including Relational Population Services (RPS)
JADE Object Manager Guide	JADE Object Manager administration
JADE Platform Differences Guide	Platform differences when running JADE applications
JADE Report Writer User's Guide	Using the JADE Report Writer to develop and run reports
JADE Runtime Application Guide	Administering deployed JADE runtime applications
JADE Thin Client Guide	Administering JADE thin client environments
JADE Web Application Guide	Implementing, monitoring, and configuring Web applications

This chapter covers the following topics.

- [Operational Requirements](#)
 - [Hardware Requirements](#)
 - [Minimum Hardware Requirements for Running JADE Thin Client Software Only](#)
 - [Minimum Hardware Requirements for Machines not Hosting a JADE Database](#)
 - [Minimum Hardware Requirements for Machines Hosting a JADE Database](#)
 - [Software Requirements](#)
 - [Additional Software Requirements for Deploying JADE Web Applications](#)
 - [ODBC Requirements for External Database Coexistence or JADE ODBC Driver Usage](#)
 - [JADE Generic Messaging Requirements](#)
 - [.NET Requirements](#)
 - [Requirement for Postscript Printing](#)
 - [Requirements for RPS Nodes](#)
 - [Virtual Environments](#)
- [Installing Your JADE Software](#)
 - [Initiating the Installation from the JADE Setup Program](#)
 - [JADE Software Installation Process](#)
- [JADE Configurations under Windows](#)
 - [Multiuser Configuration](#)
 - [Single User Configuration](#)
 - [Installing Multiple JADE Initialization Files](#)
- [Reregistering JADE with a New Licence](#)

Operational Requirements

This section describes the JADE operational requirements and contains the following subsections.

- [Hardware Requirements](#)
- [Software Requirements](#)

Hardware Requirements

This section describes the hardware required for JADE development and JADE applications running under a Windows operating system.

Further requirements that must be met to satisfactorily provide for data recoverability are described in the *Environmental Considerations for Deploying JADE* white paper on the JADE Web site at <https://www.jadeworld.com/developer-center/resource-library/white-papers>.

Notes These specifications represent minimum configurations. Configurations that are more powerful may be advisable, depending on the scale of your JADE applications and the performance requirements of your system.

JADE handles only the first nine monitors running on one workstation. Additional monitors are ignored.

For examples of some business-critical production system hardware considerations, see "Example Production System Configurations", in Chapter 3.

Minimum Hardware Requirements for a JADE Database Server

The following subsections contain the recommended minimum hardware required to deploy JADE on a machine that hosts a JADE database server node.

Processors

For a 64-bit database server with:

- Up to 10 concurrent users, you require an Intel Single Core CPU (Pentium, AMD, or compatible), 1 GHz or faster
- More than 10 concurrent users, you require an Intel Dual Core CPU (Pentium, AMD, or compatible), 1 GHz or faster

For client nodes, the default configuration also requires 64-bit binaries. However, if you require 32-bit client nodes (for example, to allow for the use of 32-bit third-party DLLs), these can be used with some loss of performance and functionality.

Memory

For database servers, you require 2G bytes Error Checking and Correcting (ECC) RAM.

Add 128M bytes for each JADE node.

Storage

For database servers, you require:

- Disk subsystem that guarantees that acknowledged writes are non-volatile (for details, see the *Environmental Considerations for Deploying JADE* white paper on the JADE Web site at <https://www.jadeworld.com/developer-center/resource-library/white-papers>)
- Available disk space of four times the expected database size, allowing for growth
- RAID 1+0 configuration (for details, see the *Environmental Considerations for Deploying JADE* white paper on the JADE Web site at <https://www.jadeworld.com/developer-center/resource-library/white-papers>)

Other

For database servers:

- Server class hardware is essential
- TCP/IP network environment is required

- Data backup components (for example, a backup disk drive, tape drive, or an optical read-write drive)

Minimum Hardware Requirements for an Application Server

The following subsections contain the recommended minimum hardware required to deploy JADE on machines hosting an application server.

Processors

For a 64-bit application server with:

- Up to 10 concurrent users, you require an Intel Single Core CPU (Pentium, AMD, or compatible), 1 GHz or faster
- More than 10 concurrent users, you require an Intel Dual Core CPU (Pentium, AMD, or compatible), 1 GHz or faster

Memory

For application servers, you require 2G bytes Error Checking and Correcting (ECC) RAM.

Add 128M bytes for each JADE node.

Storage

When computing disk space requirements for application servers, allow for software installation size, transient object storage, and application external file requirements.

Other

For application servers:

- Server class hardware is recommended
- Transmission Control Protocol/Internet Protocol (TCP/IP) network environment is required
- Data backup components (for example, a backup disk drive, tape drive, or an optical read-write drive) if not provided by another server (for example, by the database server)

Minimum Hardware Requirements for Standard Clients

The following subsections contain the recommended minimum hardware required to deploy JADE on a machine that hosts a JADE standard client.

Processors

For a standard client, you require an Intel CPU (Pentium, AMD, or compatible), 1 GHz or faster.

Memory

For standard clients, you require 512M bytes Error Checking and Correcting (ECC) RAM.

Add 128M bytes for each JADE node.

Storage

When computing disk space requirements for standard clients, allow for software installation size, transient object storage, and application external file requirements.

Other

For standard clients:

- Screen resolution of 800x600 or higher is required
- TCP/IP network environment is required

Minimum Hardware Requirements for Running Presentation Clients

The following subsections contain the recommended minimum hardware required to deploy JADE on a presentation (or *thin*) client node.

Processors

For a presentation client, you require an Intel CPU (Pentium, AMD, or compatible), 1 GHz or faster.

Memory

For presentation clients, you require 512M bytes RAM (recommended) or 256M bytes (minimum, depending on the operating system).

Storage

When computing disk space requirements for presentation clients, allow for software installation size, presentation client forms cache, and application external file requirements.

Other

For presentation clients:

- TCP/IP network environment is required
- Network Interface Card (NIC) or a dial-up adaptor and modem
- Screen resolution of 800x600 or higher is required

Software Requirements

This section describes the software required for JADE development and JADE applications.

The supported Windows operating system versions are:

- Windows Server 2016 (from JADE 7.1.09, JADE 2016.0.01, and later)
- Windows Server 2012
- Windows Server 2008 R2
- Windows 10 (from JADE 7.1.06, JADE 2016.0.01, and later)
- Windows 8.1

- Windows 8
- Windows 7

Notes The database server will run only on a 64-bit version of Windows. Clients can be 32-bit or 64-bit.

JADE encodes Unicode characters using the wide-character-encoding routines provided by Microsoft Windows.

JADE 2016 has been compiled using Microsoft Windows C++ 2013 update 4 compiler for 64-bit and 32-bit binaries. It requires the Microsoft C++ 2013 (12.0.21005.1) Redistributable Package (x64) called **vc_redist_x64.exe** or the Redistributable Package (x86) called **vc_redist_x86.exe** to be installed. (This executable is supplied on the JADE distribution media.) This redistributable package should be installed on your Microsoft Internet Information Server (IIS) server if **jadehttp.dll** is used, to ensure that **jadehttp.dll** can execute correctly.

Installation of the required C++ runtimes will be done as part of the normal JADE installation, if necessary. Installing this Microsoft redistributable package requires administration privileges.

We recommend that you keep up-to-date with Service Packs and security updates for the operating system that you are running.

JADE uses different versions of the Expat Extensible Markup Language (XML) and Web service parser for 32-bit and 64-bit installations. (For details, see <http://expat.sourceforge.net/>.) The 32-bit version and the 64-bit version are built using **expat_2.1.0**. The 64-bit version of the parser, which is stricter in enforcing validation rules, can raise exceptions in some applications.

Additional Software Requirements for Deploying JADE Web Applications

The additional software required to deploy JADE Web applications is the minimum of one of the following.

- Microsoft Internet Information Server (IIS)
- Apache 2.4.10 for Microsoft Windows

In addition, JADE Web services support SOAP version 1.1 and version 1.2.

Notes Unicode Web applications are not supported.

To provide greater security with firewalls, the machine hosting the Web server can be different from the machine that is running the JADE application.

ODBC Requirements for External Database Coexistence or JADE ODBC Driver Usage

The Microsoft Data Access Components (MDAC) installed with the Windows operating system are sufficient for running an external relational database or using the JADE ODBC standard or thin client driver.

Note The JADE ODBC drivers are available in 32-bit and 64-bit versions. If running on a 64-bit machine, the driver used must match the third-party tool being used; for example, it may be necessary to install 32-bit JADE ODBC drivers for use with 32-bit tools.

When using an external database on a 64-bit machine, the bit version of the JADE node executing the external database access must match the bit version of the external database ODBC driver that is being used.

If you are running JADE on a 64-bit machine under Windows in 64-bit mode and you are configuring a 32-bit ODBC driver, run the following program:

```
<\windows-directory>\SysWOW64\odbcad32.exe
```

This runs the 32-bit version of the Microsoft Data Source Administrator program rather than the 64-bit version.

For more details, see "[Configuring a JADE ODBC Driver](#)", in Chapter 2 of the *JADE External Interface Developer's Reference*.

JADE Generic Messaging Requirements

The IBM WebSphere MQ interface in the JADE Generic Messaging module is built using the WMQ version 7.0.1.3 Client interface library.

The WMQ API can be used in both 64-bit and 32-bit client nodes.

.NET Requirements

To develop and compile .NET applications for .NET exposure, you require a *minimum* of:

- Microsoft Visual Studio 2010
- Microsoft Visual Studio 2010 Express, the free but limited edition of Visual Studio 2010

Note Microsoft Visual Studio 2013 is recommended.

For external component libraries, you require:

- .NET 4.x components (or .NET 3.x, if you are using components designed for .NET 3.x)

Requirement for Postscript Printing

If using Postscript printing, your printer must support Postscript level 2 or greater.

Requirements for RPS Nodes

With the Relational Population Service (RPS), the following 64-bit SQL Server ODBC drivers must be used for the SQL Server versions.

- Microsoft SQL Server 2014 requires SQL Server Native Client 11.0 or later
- Microsoft SQL Server 2012 requires SQL Server Native Client 11.0 or later
- Microsoft SQL Server 2008 requires SQL Server Native Client 10.0 or later
- Microsoft SQL Server 2005 requires SQL Native Client or later
- Microsoft SQL Server 2000 requires SQL Native Client or later (recommended) or SQL Server

The **sqlcmd** SQL Server utility must be installed on the RPS node to use the default (recommended) **sqlcmd** to execute SQL scripts. (For details, see step 6.e under "[Configuring your RPS Node](#)", in Chapter 2 of the *JADE Synchronized Database Service (SDS) Administration Guide*.)

Virtual Environments

JADE can be run in a virtual environment on all supported operating systems listed in the previous sections on Intel-compatible hardware.

Support is provided as per the published release policy for faults found in a virtual environment; however, a problem that is suspected to be related to an issue in the virtualization layer may result in requests for additional customer diagnostic actions. In some rare cases, fixes for issues that are specific to the virtualization layer may need to be negotiated with the customer.

Installing Your JADE Software

The JADE software is supplied on the JADE release medium or from the JADE Web site. Install your JADE software from the **setup** executable program file contained on the release medium or from the JADE Web site.

Notes If you want to develop your own installation process for Windows, the JADE install and upgrade steps are documented in the **ReadmeInstallSteps.pdf** file in the documentation directory.

Installing any Microsoft redistributable package requires administration privileges.

The 32-bit and 64-bit Microsoft C++ 2013 Redistributable Package (x64) called **vc_red.msi** or the 32-bit Microsoft C++ 2013 SP1 Redistributable Package (x86) called **vc_red.msi** is required on all Windows systems that run JADE 2016.

Click the **Next >** button when you have specified the required information in each JADE set-up folder. The folder for the next phase of the installation process is then displayed, if applicable. Use the **< Back** button to return to earlier set-up folders. To abandon the JADE installation, click the **Cancel** button in the current set-up folder.

For details about customizing the upgrading of deployed JADE systems, see Appendix A of the *JADE Runtime Application Guide*, "[Customizing the Deployment Upgrade Process](#)".

Note Example files are not part of the installation and must be downloaded and installed from the JADE Web site separately, if required.

Initiating the Installation from the JADE Setup Program

» To initiate the installation of your JADE software

1. Ensure that you have the appropriate privileges to install applications.
2. Double-click the executable program downloaded from the JADE Web site (<https://www.jadeworld.com/developer-center/download-jade>).

The installation of your JADE software is then started and the initialization progress is displayed in the Setup progress dialog.

JADE Software Installation Process

During the installation process, the JADE set-up program performs the events described in the following subsections.

Displaying the Welcome Dialog

The JADE set-up program first displays the Welcome dialog.

Accepting the Terms of the JADE License Agreement

The Software License Agreement folder is then displayed. Use the scroll bar or the Page Down key to scroll through and read the entire software license agreement.

When you have read the entire software license agreement and you accept the specified terms, click the **Yes** button to continue the installation. (You cannot install JADE until you accept these license agreement terms.) Alternatively, click the **No** button to close the JADE set-up process.

Selecting the Type of Installation

The Installation Type folder is then displayed, to enable you to select the type of installation that you require. The types of installation that you can select are:

- **Fresh Copy**, which is selected by default, and installs a brand new copy of JADE.
- **Feature Upgrade**, which you can select if you want to upgrade an existing JADE database or binary files, or both database and binary files. For details, see the [ReleaseInfo.pdf](#) file on your JADE release medium.

Selecting the Type of Set Up

The Setup Type folder is then displayed, to enable you to select the type of set up that you require.

The types of set up that you can select are listed in the following table.

Type	Installs...
Development	Binary, database, JADE Report Writer, and general support files required to run single user and multiuser mode of the development and application runtime environments and JADE application server and presentation client files (64-bit only)
Application Runtime	Only the binary and general support files required to run the JADE application server
Presentation Client	Only the binary and general support files required to run the presentation client in JADE thin client mode
Jade Client	Only the binary files and general support files required to run a JADE client
Custom	User-selected JADE components (for the Fresh Copy installation type only)
SDS development	Binary and database files for the JADE environment on SDS (Feature Upgrade installation type and 64-bit only)

By default, the **Development** option is selected for 64-bit, or **Jade Client** for 32-bit.

Selecting the Components to Install

When you specify a **Custom** installation, the Select Components folder is then displayed, to enable you to select the file components that you want to install. You can select the installation of the following components.

- Binary Files
- Include Files
- Library Files

- Presentation Client Files (64-bit, 32-bit)
- ReadMe File
- Report Writer Files (JADE Report Writer)
- System Files (JADE development database), 64-bit only
- WSDL Files

No components are selected for installation, by default.

» To select or deselect a component for installation

- Click the appropriate component.

The disk space required for each component is displayed at the right of the component in the **Components** list box.

The available disk space and the required disk space for all currently selected components are displayed at the bottom of the folder.

Specifying Your User Information

If you are installing a JADE database, the User Information folder enables you to specify the **Licence Name** (that is, your organization name, which is not to be confused with your company name that is displayed in large letters above the licence name and key) and your **Licence Key** specified on your licence for your JADE database.

An entry is required in both the **Licence Name** and **Licence Key** text boxes.

Notes To obtain your licence key, contact your local JADE authorized reseller.

The licence key has four text boxes. Enter the licence key *exactly* as it is specified on your Certificate of Authorisation (which may be an e-mail message providing you with your licence name and key). Enter the first eight characters in the first text box, the next eight characters in the second text box, the next eight characters in the third text box, and the last eight characters in the fourth text box. (Ignore the "-" printed on the licence.)

Ensure that you type the licence name of your organization (which is case-sensitive) correctly, as this is validated against your licence key.

Selecting the Destination Directory

The Select Installation Folders folder enables you to specify the locations of the JADE files that are to be installed. The installation process defaults to the **Jade71** directory on your **c:** drive, and displays these values in the **Install Directory**, **Executable Directory**, and **Database Directory** text boxes.

» To select a destination directory

- Click the **Browse** button.

The common File dialog is then displayed, to enable you to specify the destination directory for your JADE files.

The **Database Directory** text box enables you to explicitly specify the location in which the database (system) files are installed. When the destination folder is not **Program Files**, the database destination defaults to **system** under the install folder (for example, if you specify **c:\Jade71** in the **Install Directory** text box, the database directory defaults to **c:\Jade71\system**).

If the installation directory is a subdirectory of the programmatically determined location of **\Program Files**, the **\Program Files** portion of the install directory is replaced with programmatically discovered location for the common application data directory (for example, if you specify **c:\Program Files\Jade71** in the **Install Directory** text box, the default database location is **c:\ProgramData\Jade71\system**).

Selecting the Program Folder for the JADE Icons

The Select Program Folder folder is then displayed, to enable you to select the program folder in which the JADE icons are installed.

By default, the JADE icons are installed in the **JADE** program folder. If the program folder specified in the **Program Folder** text box does not exist, the installation process creates it.

The **Existing Folders** list box enables you to select an existing program folder, if required.

Running the Installation Program

The Start Copying Files folder is then displayed. This dialog displays the installation options that you have selected.

Review your selections and then click the **Next >** button, to start copying files.

Informing You When the Installation is Complete

When the installation is complete, the JADE set-up program informs you that the JADE set-up program was successfully completed and the **ReadMe.txt** file can now be viewed.

» To view the ReadMe.txt file

- Ensure that the check box is checked (the default).

The **ReadMe.txt** file, which refers you to the document covering upgrading to JADE release 7.1, the changes and new features in this release, and to other documents relating to JADE release 7.1, is then displayed in a text editor (for example, Notepad).

The **ReadMe.txt** file is a read-only text file installed in your JADE **documentation** directory that you can print or delete, if required.

Click the **Finish** button to end the JADE installation process. Alternatively, if a system file could not be updated, the JADE set-up program prompts you to reboot your workstation so that it can complete the installation. In this case, you can view the **ReadMe.txt** file by using the shortcut in your specified folder.

JADE Configurations under Windows

The JADE database can be run in one of the following configurations.

- Multiuser (the default)

The multiuser configuration allows access to the database from multiple processes across multiple workstations. One workstation must perform the role of server, or remote, node. For more details, see "[Multiuser Configuration](#)", in the following subsection.

- Single user

The single user configuration allows access to the database from one process only (for example, only one copy of **jade.exe**). For more details, see "[Single User Configuration](#)", later in this chapter.

For details about accessing JADE applications from IIS or the Apache HTTP Server, see "[Connecting to JADE Applications from Internet Information Server \(IIS\)](#)" and "[Configuring JadeHttp for Remote Connections](#)" or see "[Connecting to JADE Applications from an Apache HTTP Server](#)" and "[Configuring Apache for Remote Connections](#)", in Chapter 3.

Multuser Configuration

Before running JADE in multuser mode (the default), ensure that TCP/IP has been loaded on both your client workstations and the server (remote node) workstation. For details, see "[Selecting Network Addresses](#)", in Chapter 3, or "[Using the JADE Remote Node Access Utility](#)", in Chapter 1 of the *JADE Remote Node Access Utility User's Guide*.

In the standard initial installation, the following parameters are set in the **jade.ini** file in the database directory.

```
[Jade]
server=multiUser           // Default

[JadeServer]
NodeName=localhost
NetworkSpecification1=TCP,Enabled,6005

[JadeClient]
ServerNodeSpecifications=TCP,localhost,6005
```

This sets up the server and clients to run on the same installation node. (TCP is case-insensitive in JADE initialization file parameter values.)

For more details about the parameters in the JADE initialization file required to run JADE in a multuser environment, see Chapter 1 of your *JADE Initialization File Reference*, particularly the "JADE Object Manager Client Module Section [[JadeClient](#)]" and "JADE Object Manager Server Section [[JadeServer](#)]" sections.

For details about using the server Uniform Resource Identifier (URI) string so that a client node can specify the target database server and transport details, see "[Format of the Server URI String](#)", in Chapter 3.

Running a JADE Server in Multuser Mode

The default multuser installation sets up the **JADE MultiUser \JADE Database Server** shortcut for the JADE server.

The following table lists examples of the properties required to run a JADE server.

Property	Example
Command line	jadrap.exe path=s:\jade\system ini=s:\jade\system\jade.ini app=Jade
Working directory	s:\jade\bin

Running a JADE Client in Multuser Mode

The default multuser installation sets up the **JADE MultiUser \JADE Client** shortcut for the JADE multuser client.

Tip When running JADE in multuser mode as a standard (fat) client, the JADE initialization file is usually specified on the command line. If a JADE initialization file is not specified, JADE attempts to use the **jade.ini** file in the server node **system** directory.

If this directory is not visible to the client node, the default values used may not be sufficient for your application to run.

The following table lists examples of the properties required to run the JADE development environment in a JADE client.

Property	Example
Command line	jade.exe path=s:\jade\system ini=c:\jade\system\jade.ini app=Jade
Working directory	s:\jade\bin

Ensure that you specify the same path in the **path** parameter of both the JADE Remote Node Access utility (**jadrap**) and JADE (**jade.exe**).

Running a JADE User Application in Multiuser Mode

The following table lists examples of the properties required to run a user application written in JADE on a client node.

Property	Example
Command line	jade.exe path=s:\jade\system schema=AccountsApp app=Accounts ini=c:\jade\system\jade.ini
Working directory	s:\jade\bin

Ensure that you specify the same path in the **path** parameter of both the JADE Remote Node Access utility (**jadrap**) and JADE (**jade.exe**).

Running an Application Server in JADE Thin Client Mode

The default multiuser installation sets up the **JADE MultiUser \ Jade Application Server** shortcut for the JADE application server.

The following table lists examples of the properties required to run an application server in JADE thin client mode.

Property	Example
Command line	jadapp.exe appServerPort=1500 server=multiUser path=s:\jade\system ini=s:\jade\system\jade.ini
Working directory	s:\jade\bin

For more details, see "[Invoking an Application Server](#)", in Chapter 2 of the *JADE Thin Client Guide*.

Running a Presentation Client in JADE Thin Client Mode

The default multiuser installation sets up the **JADE MultiUser \JADE Presentation Client** shortcut for the JADE presentation client.

The following table lists examples of the properties required to run a presentation client in JADE thin client mode.

Property	Example
Command line	D:\JADE\bin\jade.exe app=SortApp schema=SortTest appServer=JadeServer appServerPort=1500
Working directory	D:\jade\bin

If a JADE initialization file is not specified on the command line when you are running an application in thin client mode, JADE attempts to use the **jade.ini** file in the installation directory of **jade.exe** (that is, the **bin** directory) on the presentation client node.

For more details, see "[Invoking a JADE Presentation Client](#)", in Chapter 2 of the *JADE Thin Client Guide*.

Single User Configuration

Before you run JADE in single user mode, ensure that the **Server** parameter in the **[Jade]** section of the JADE initialization file is set to **singleUser**. Alternatively, you can specify **server=SingleUser** in the command line.

Running JADE in Single User Mode

The default installation sets up the **JADE** shortcut for a single user mode client. The following table lists examples of the properties required to run the JADE development environment in single user mode.

Property	Example
Command line	<code>jade.exe path=c:\jade\system ini=c:\jade\system\jade.ini app=Jade server=singleUser</code>
Working directory	<code>c:\jade\bin</code>

Running a JADE User Application in Single User Mode

The following table lists examples of the properties required to run a user application written in JADE in single user mode.

Property	Example
Command line	<code>jade.exe path=c:\jade\system ini=c:\jade\system\jade.ini schema=TPC_A app=BenchmarkApp server=SingleUser</code>
Working directory	<code>c:\jade\bin</code>

Installing Multiple JADE Initialization Files

If you want multiple users to share binary files on your Local Area Network (LAN), install multiple copies of the JADE initialization file. For example, you can install multiple initialization files so that each user has his or her own initialization file.

» To install multiple JADE initialization files

1. Copy the JADE initialization file (**jade.ini**) into the appropriate user directory.
2. Create a JADE shortcut to meet your requirements, with the **ini** parameter in the command line specifying the JADE initialization file of the user; for example:

```
c:\jade\bin\jade.exe ini=c:\current\myjade.ini path=c:\jade\system
schema=Faults server=singleUser app=Jade
```

The *working-directory-name* is usually the directory in which the JADE executable file (**jade.exe**) is located but you can specify another start-in directory when you install JADE, if required. The parameters can be in any order but must be specified once only.

For details about multiple JADE programs on the same host sharing a JADE initialization file, see "[Sharing JADE Initialization Files](#)", in the *JADE Initialization File Reference*.

Reregistering JADE with a New Licence

The **JadReg** program installed with your JADE software enables you to reregister JADE with new licence information.


Note JADE licenses are not transferred automatically between databases in an SDE. It is your responsibility to apply new licenses to any existing databases in an SDE. In addition, to ensure proper operation, you must apply the primary license to every secondary.

For details about automating the registration of a JADE system by running the registration program in batch mode, see "[Reregistering a JADE System in Batch Mode](#)", in Chapter 3.

» To reregister JADE

1. In Explorer or File Manager, access the directory in which your JADE binary files are located (for example, **c:\jade\bin**) and then double-click the **jadreg** program.

The Jade Registration Update dialog, shown in the following image, is then displayed.



2. In the **Database Directory** combo box, specify your JADE database directory or select it from the drop-down list. The last system directory that was accessed is displayed by default.
3. If you want to update your licence without stopping the JADE server, enter the name and absolute path of the JADE initialization file in the **Ini File** text box and then check the **Online** check box. This enables the **jadreg** program to obtain multiuser initialization file settings that will allow it to sign on to the JADE Remote Node

Access utility (**jadrap**).

Wait until the **jadreg** program has signed on successfully before proceeding to the next step.

Note You must specify the absolute path and name of the JADE initialization file before you check the **Online** check box.

You must close down the JADE server before you can update your licence key if you do not specify that you want online registration update.

- In the **Licence Name** text box, specify your organization's licence name (displayed on your Certificate of Authorisation, which may be an e-mail message providing you with your licence name and key).

Note This must be typed correctly (it is case-sensitive), as it is validated against your licence key.

- In the **Licence Key** text boxes, specify your licence key for your JADE database.

Enter the licence key exactly as specified on your Certificate of Authorisation. Enter the first eight characters in the first text box, the next eight characters in the second text box, the third eight characters in the third text box, and the last eight characters in the fourth text box. (Ignore the "-" printed on the Certificate of Authorisation.)

- Server licences are split over the two types of run time operation; that is, standard (fat client) and JADE thin client. You can optionally specify the minimum number of licences reserved for both types of run time operation, if required, by performing the following step.

In the **Minimum Usage** text boxes, specify the minimum number of runtime licences you want reserved for:

- **Standard Jade** (that is, standard fat client runtime licences)
- **Thin Jade** (that is, JADE thin client runtime licences)

Specify minimum values for both types of runtime licence so that when you run your JADE applications, you can ensure that a specific number of licences are available (reserved) for that type of operation at any time.

Note You cannot specify a minimum number of licences greater than the number of your registered server (run time) licences.

The default value of zero (**0**) indicates that there is no minimum number of licences for each run time type. (For details about viewing the minimum number of JADE licences that you specify in this dialog and monitoring the number of licences that are available and currently in use, see "[Displaying the Licence Information View](#)", in Chapter 2 of the *JADE Monitor User's Guide*.)

- Click the **Update** button.

The dialog then displays the following information.

- The type of licence is displayed at the bottom of the JADE development environment sign-on screen; that is, an unrestricted primary (**Production**) licence or an **Enterprise** or **Free** restricted licence.

A user application developed using an **Enterprise** or **Free** restricted licence that is invoked from outside of the JADE development environment displays a splash screen that states that the application is not for production use. The only action that the user can perform is to click anywhere on the splash screen or to press any key to remove the splash screen.

- The number of developer, process, and secondary database licences for which you are registered at run time.
- If your licence is not perpetual, the expiry date of the licence.

If you specified an invalid licence name or licence key, a message box is displayed, advising you of the invalid entry.

8. Click the **Close** button.

This chapter covers the following topics.

- [Example Production System Configurations](#)
- [Directory Locations](#)
- [Configuring Your Network Protocol](#)
 - [Selecting Network Addresses](#)
 - [TCP/IP Transport](#)
 - [Hybrid Pipe Shared Memory \(HPSM\) Transport](#)
 - [JadeLocal Transport](#)
 - [Format of the Server URI String](#)
 - [Server Thread Model](#)
- [Connecting to JADE Applications from Internet Information Server \(IIS\)](#)
- [Connecting to JADE Applications from an Apache HTTP Server](#)
- [Configuring Your JADE Software](#)
 - [Configuring the Internet Protocol Version](#)
 - [RPC, Database, and Node Configuration](#)
 - [Configuring JadeHttp for Remote Connections](#)
 - [Firewall for the JADE Internet Environment](#)
 - [Controlling the Location of Files Uploaded via a Web Application](#)
 - [\[application-name\] Section](#)
 - [\[Jadehttp Files\] Section](#)
 - [\[Jadehttp Logging\] Section](#)
 - [Configuring Apache for Remote Connections](#)
 - [Tuning Your Systems](#)
- [Specifying Parameters in the JADE Command Line](#)
- [Specifying Your Administration Options](#)
- [Reregistering a JADE System in Batch Mode](#)
- [Using the JADE Version Information Utility](#)
- [Using the JADE Sentinel Process Dumps Program](#)

Example Production System Configurations

The following table represents some business-critical production system hardware configurations as at July 2007. These are intended as indicative examples only.

More-powerful configurations may be required, depending on the scale of your JADE applications and the performance requirements of your system.

Note In the following table, all CPUs are Intel or Intel-compatible.

Peak Users	Nodes	Database Size	Hardware Description
8	1	5G bytes	Single server <ul style="list-style-type: none"> ■ 1 x single core 1 GHz CPU ■ 2G bytes ECC RAM ■ 2 x 72G bytes 15K drives (database/OS) ■ 2 x 72G bytes 15K drives (journals/backup)
15	2	8G bytes	Single server <ul style="list-style-type: none"> ■ 1 x Dual Core 1 GHz CPU ■ 2.5G bytes ECC RAM ■ 2 x 72G bytes 15K drives (database/OS) ■ 2 x 72G bytes 15K drives (journals/backup)
190	20	80G bytes	Two servers, clustered, each server with: <ul style="list-style-type: none"> ■ 2 x single core 3.4 GHz CPUs with Hyperthreading ■ 5G bytes ECC RAM ■ 2 x 72G bytes 15K drives (OS/workspace) Storage Area Network (SAN) containing: <ul style="list-style-type: none"> ■ 8 x 72G bytes 15K drives (database) ■ 2 x 144G bytes 15K drives (journals) ■ 4 x 300G bytes 15K drives (backup)
225	13	115G bytes	Single server <ul style="list-style-type: none"> ■ 4 x single core 3 GHz CPUs with Hyperthreading ■ 7.5G bytes ECC RAM ■ 10 x 72G bytes 15K drives (database) ■ 2 x 144G bytes 15K drives (journals) ■ 8 x 144G bytes 15K drives (backup)
350	24	240G bytes	Single server <ul style="list-style-type: none"> ■ 8 x single core 3 GHz CPUs ■ 20G bytes ECC RAM ■ 2 x 144G bytes 15K drives (OS/workspace)

Peak Users	Nodes	Database Size	Hardware Description
200	17	250G bytes	<p>SAN containing:</p> <ul style="list-style-type: none"> ■ 28 x 144G bytes 15K drives (database) ■ 20 x 144G bytes 15K drives (backup/journals) <p>Two servers, clustered, each server with:</p> <ul style="list-style-type: none"> ■ 8 x single core 2 GHz CPUs ■ 6G bytes ECC RAM ■ 2 x 144G bytes 15K drives (OS/workspace) <p>SAN containing:</p> <ul style="list-style-type: none"> ■ 20 x 72G bytes 15K drives (database) ■ 20 x 144G bytes 15K drives (backup/journals)

Directory Locations

The ability to return locations other than the JADE HOME directory for program and user data requests is dependent on where the JADE binaries have been installed. If the JADE programs are installed in the **Program Files** system-wide location for installed applications, alternative directory locations are implemented.

Because security restrictions can deny appropriate access to directories or the directories are a unique location for each user, the **Node** and **Process** classes provide methods that enable you to access other directory locations in the file system hierarchy. In addition, the [JadeEnvironment] section of the JADE initialization file provides the **JadeWorkDirectory**, **ProgramDataDirectory**, and **UserDataDirectory** parameters, which enable you to specify the location of JADE work files, program data, and user data, respectively.

In the methods summarized in the following subsections, a method on a specific:

- Node instance performs its action on the specified node instance, which does not have to be the current node. If the current node is required, use the **node** environmental object (system variable).
- Process instance performs its action on the owning node (that is, a **Process.node** instance) if the process is not associated with a presentation client. If the process has an associated presentation client, the action is performed on the presentation client. The presentation client does not have to be the current presentation client or a presentation client attached to the same application server.

For details, see [Volume 1](#) and [Volume 2](#) of the *JADE Encyclopaedia of Classes* and "JADE Environment [JadeEnvironment] Section", in the *JADE Initialization File Reference*.

Installation Directory Location

The **getJadeInstallDirectory** method defined in the **Node** and **Process** classes returns a string containing the directory in which the executable of the current executing program is located; that is, the directory in which the JADE binaries are installed.

See also "[Work File Directory Location](#)", later in this chapter.

Home Directory Location

The **getJadeHomeDirectory** method defined in the **Node** and **Process** classes returns a string containing the parent directory of the installation directory.

Program Data Directory Location

The `getProgramDataDirectory` method defined in the `Node` and `Process` classes returns a string containing the program data directory, which is dependent on the:

- Value of the `ProgramDataDirectory` parameter in the `[JadeEnvironment]` section of the JADE initialization file. The parameter is read each time the `getProgramDataDirectory` method is called. When you call this method and the directory does not already exist, JADE creates it based on the value of the `ProgramDataDirectory` parameter.
- Location of the installation directory.

Files that should be placed under the returned location are entities that should be shared across multiple users of these binaries; for example, the `jommsg.log` file or shared dictionary spelling files that are updated.

If the installation directory is a subdirectory of the programmatically determined location of `\Program Files`, translation rules are applied. However, if the installation directory is not a subdirectory of the `\Program Files` location, the return value is the same as the JADE HOME directory.

The `ProgramDataDirectory` parameter in the `[JadeEnvironment]` section of the JADE initialization file can have one of the following values.

- `<default>`, which is the default value

The `<default>` value has the same meaning as the `<programdata>` value.

- `<homedir>`

The value of the JADE HOME directory is returned.

- `<programdata>`

The `\Program Files` portion of the HOME directory is replaced with the programmatically obtained location for the common application data directory. For example, a presentation client installed into `\Program Files\Jade Software Corporation\parsys` returns `\ProgramData\Jade Software Corporation\parsys`.

- A user-specified directory name, which returns the specified directory

The directory location is created, if necessary, and returned in the required format.

User Data Directory Location

The `getUserDataDirectory` method defined in the `Node` and `Process` classes returns a string containing the user data directory, which is dependent on the:

- Value of the `UserDataDirectory` parameter in the `[JadeEnvironment]` section of the JADE initialization file. The parameter is read each time the `getUserDataDirectory` method is called. When you call this method and the directory does not already exist, JADE creates it based on the value of the `UserDataDirectory` parameter.
- Location of the installation directory.

Files that should be placed under the returned location are entities that should be unique to each user of these binaries; for example, if a presentation client installation occurs on a Windows machine running Citrix or Terminal Services and all users run the same thin client binaries, any data created on the client file system should be stored under this location (that is, unique dictionaries for each user).

If the installation directory is a subdirectory of the programmatically determined location of `\Program Files`, translation rules are applied. However, if the installation directory is not a subdirectory of the `\Program Files` location, the return value is the same as the JADE HOME directory.

The **UserDataDirectory** parameter in the [JadeEnvironment] section of the JADE initialization file can have one the following values.

- **<default>**, which is the default value

The **<default>** value has the same meaning as the **<userdata>** value.

- **<homedir>**

The value of the JADE HOME directory is returned.

- **<userdata>**

The **\Program Files** portion of the HOME directory is replaced with the programmatically determined location for the specific user application private data directory. For example, a presentation client installed into **\Program Files\Jade Software Corporation\parsys** and executed by user **wilbur** returns **\Users\wilbur\AppData\Local\Jade Software Corporation\parsys**.

- A user-specified directory name, which returns the specified directory

The directory location is created, if necessary, and returned in the required format.

Work File Directory Location

The **getJadeWorkDirectory** method defined in the **Node** and **Process** classes returns a string containing the JADE work directory, which is dependent on the:

- Value of the **JadeWorkDirectory** parameter in the [JadeEnvironment] section of the JADE initialization file. The parameter is read each time the **getJadeWorkDirectory** method is called and the directory is accessed. When you call this method and the directory does not already exist, JADE creates it based on the value of the **JadeWorkDirectory** parameter.
- Location of the JADE HOME directory.

By default, the **jade.exe** executable program file does not directly create or update files in the binary directory.

- The **JadeWorkDirectory** parameter in the [JadeEnvironment] section of the JADE initialization file determines the directory in which work files are created.

By default, this directory is created at the same level as the JADE binary directory and is named **temp**. For example, the directory is named **c:\jade\temp** if the JADE installation directory is **c:\jade\bin**.

The **JadeWorkDirectory** parameter can specify an absolute path or a relative path (relative to the JADE HOME directory, which is **c:\jade** in the above example).

- The presentation cache file is written into the directory defined by the value of the **JadeWorkDirectory** parameter unless the **FormCacheFile** parameter in the [JadeThinClient] section of the JADE initialization file specifies the location of the form cache file.
- The presentation client automatic download process lock files are created in the directory specified by the **JadeWorkDirectory** parameter.
- The automatic presentation client download **log** file is written to the location specified by the **LogDirectory** parameter in the [JadeLog] section of the JADE initialization file.

The only situations in which a file creation or update will occur within the JADE binary directory are as follows.

- If the JADE initialization file is positioned in the binary directory (the default action for a presentation client). You can avoid this by using the **ini** parameter in the JADE presentation client command line to specify an alternative location on initiation of the presentation client.

- When the **jaddin**st executable program installs files downloaded by the JADE thin client automatic download facility.

Configuring Your Network Protocol

TCP/IP is required for multiuser configurations. TCP/IP must be installed on each workstation that is to participate as a node in the JADE environment. Your network manufacturer supplies TCP/IP and your network administrator supplies the TCP/IP address.

JADE also provides fast transport mechanisms for JADE modules on the same machine (for example, one that has multiple CPUs). For details, see "[Hybrid Pipe Shared Memory \(HPSM\) Transport](#)" and "[JadeLocal Transport](#)", later in this chapter.

Use the:

- **NetworkSpecification** parameter in the [[JadeServer](#)] section of the JADE initialization file to specify the transport types used by a JADE server.
- **ServerNodeSpecifications** parameter in the [[JadeClient](#)] section of the JADE initialization file to specify the transport type used by a JADE client to connect to the server.
- Server URI string in the **server** parameter of a command line, to specify the target database and the client-server transport. For details, see "[Format of the Server URI String](#)", later in this chapter.

As JADE database servers and JADE application servers can often reside on the same machine, you can use a local intra-machine transport to significantly improve performance. You can also use these transport mechanisms to communicate from standard (fat) clients and JADE application servers to JADE servers if these processes run on the same physical machine, to significantly improve overall performance. Intra-machine local transport uses *shared memory*.

To detect whether a connection has been lost, a polling mechanism ensures that some minor communication is taking place regularly. See also "[TransportIdlePollInterval](#)" under "JADE Object Manager Server Section [[JadeServer](#)]", in the *JADE Initialization File Reference*.

If your database is running as a service but not with the **Local System** account, your Windows administrator must configure the user logon to add the following Windows privilege **Create global objects (SeCreateGlobalPrivilege)** at the programming API level), which can be done directly to the user logon or to a group of which that user is a member. On a machine that is not part of a Windows domain, this can be done by accessing the **Local Security Policy** in the Administrative tools directory and adding the **Create global objects** policy under **Local Policies / User Rights Assignment** to the desired group or user. This allows JADE programs that need to connect via the **JadeLocal** or **HPSM** intra-machine transport to work across multiple Windows sessions or user logons.

With the **HPSM** transport, a database running with a standard account requires the extra privilege. Client nodes do not require the extra privilege.

With the **JadeLocal** and **HPSM** transports, if a standard user attempts to create a **Globalbasetname** value in either of these initialization file parameters, it fails because of insufficient privileges.

Selecting Network Addresses

Use the reserved range of Class C network addresses if you want to set up a small private network for demonstration purposes. (The reserved private Class C network addresses are in the range **192.168.0** through **192.168.255**, and are often used for broadcast messages.) If you therefore select network number **192.168.1**, for example, you can then assign all IP addresses for your host in the range **192.168.1.1** through **192.168.1.254**.

Ensure that the first three parts of this address are the same for all interfaces connected to the same LAN segment, and set the subnet mask to **255.255.255.0**.

Tip Choose a reserved private Class C IP address when one or more of the workstations also needs to connect to the Internet by using an Internet Service Provider (ISP). If you use these reserved addresses, they should not conflict with any valid Network Interface Controller (NIC)-assigned Internet addresses. Avoid using random numbers for IP addresses, as this usually fails.

When you have configured your network and IP addresses, check that workstations can see each other using the IP protocol. A simple test is to use **ping** from a command prompt, by entering one or both of the following command prompts from any workstation:

```
ping computer-name
ping remote-IP-address
```

If this does not provide a response, you will not be able to use the specified workstation name as the server node name in the **ServerNodeSpecifications** parameter of the **[JadeClient]** section of your JADE initialization file.

If the IP is functioning correctly and the **ping remote-IP-address** command prompt provides a positive response, setting the **ServerNode** parameter to the server node IP address value in the **ServerNodeSpecifications** parameter in the **[JadeClient]** section of your JADE initialization file should work. Setting this **ServerNode** parameter to the workstation name of the server node may not always work even if the **ping server-node-computer-name** command prompt gives a valid response, as this alias to standard TCP/IP cannot always be relied on to work.

If you do not have Windows Internet Naming Services (WINS) or a Domain Name Server (DNS) server, you should set up a hosts file with IP address-to-name mappings and then use the names from there. If you have a small single-segment LAN and you do not know what Dynamic Host Configuration Protocol (DHCP)/DNS or WINS are, do not use them for your local networking. Only an experienced network administrator should set these up. (If you have Internet access, you will almost certainly have DNS configured.)

TCP/IP Transport

The TCP/IP transport must be used when the database server and client are on different computers. For connections on the same computer, the fast Hybrid Pipe Shared Memory (**HPSM**) transport is recommended, although TCP/IP or the **JadeLocal** transport can be used. See also "**RPC, Database, and Node Configuration**", later in this chapter.

The following JADE initialization file parameters are required to use the TCP/IP transport.

```
[JadeServer]
NetworkSpecification<n>=transport-type,enabled|disabled,
    listener-port[, interface]

[JadeClient]
ServerNodeSpecifications=transport-type,remote-host,remote-port
    [, local-interface[, local-port]]
```

Alternatively, use the **server** parameter in a command line to specify the server Universal Resource Identifier (URI) target database and the client-server transport, instead of the **server** and **path** parameters in a command line and the **ServerNodeSpecifications** parameter in the **[JadeClient]** section of the JADE initialization file. For details, see "**Format of the Server URI String**", later in this chapter.

The values (which are case-insensitive) for the *transport-type* variable in the **NetworkSpecification** parameter are:

- **TcpIP**, which is a synonym for **TcpIPv4**.
- **TcpIPv4**, which provides IP version 4 connections only.

- **TcpIPv6**, which provides IP version 6 connections only.

If you want the server to support both network protocols, you must define a network specification for each protocol.

You can specify the *interface* value as a host name or an IP address. If you use an IP address, the address must be in an appropriate format for the specified *transport-type* value. Specify the local interface name or IP address if you want to select a specific network adapter in a database server node that has more than one network adapter installed; for example, to enable an administrator to ensure connections from clients connect on the fastest interface or to allow easier security when used in conjunction with a firewall or router access list. (JADE defaults to all network adapters in the node.)

The values for the *transport-type* variable in the **ServerNodeSpecifications** parameter are:

- **TcpIP**, which is a synonym for **TcpIPAny**.
- **TcpIPAny**, which connects using IP version 4 or 6.
- **TcpIPv4**, which connects using IP version 4.
- **TcpIPv6**, which connects using IP version 6.

You can specify the *remote-host* and *local-interface* values as a host name or an IP address. If you use an IP address, the address must be in an appropriate format for the specified *transport type* value. If you specify a host name, all DNS-provided addresses will be attempted.

For the **TcpIPAny** transport type, the client will first attempt to connect via IP version 6 and then IP version 4 protocol on the provided IP addresses. Each connection failure will be logged, and the next available combination tried.

Hybrid Pipe Shared Memory (HPSM) Transport

Hybrid Pipe Shared Memory (**HPSM**) provides a fast transport mechanism between JADE nodes on the same computer to utilize the multiple CPUs and *shared memory*, to significantly improve overall performance. (An older shared-memory transport, called **JadeLocal**, is documented in the following section.)

The Remote Procedure Call (RPC) **jomsrvr2.dll** includes a Hybrid Pipe Shared Memory (HPSM) transport, which has lower overhead than the **JadeLocal** (shared memory) transport and it is a better fit with the server thread model, as it results in fewer thread context switches per request.

Note The HPSM transport can be used only between nodes residing in the same machine, because it uses shared memory.

The following JADE initialization file parameters are required to use the HPSM transport.

```
[JadeServer]
NetworkSpecification1=HPSM,enabled|disabled,[Global\]base-name

[JadeClient]
ServerNodeSpecifications=HPSM,[Global\]base-name
```

The following is an example of the required JADE initialization file definitions to use the HPSM transport.

```
[JadeServer]
NetworkSpecification1=HPSM,Enabled,TestCRM-HPSM

[JadeClient]
ServerNodeSpecifications=HPSM,TestCRM-HPSM
```

The *base-name* value can have an optional **Local** or **Global** prefix.

When the **Local** prefix tag is specified (or no prefix tag is specified), the value of the *base-name* variable is created in the session namespace. To establish a connection, the JADE database server and the JADE client must be running under the same user logon and in the same Windows session. This would not be the case, for example, if you were running an interactive desktop application that attempted to connect to the JADE database server.

When the **Global** prefix tag is specified, the *base-name* variable is created as a global object that is visible across sessions and logons.

Note Use the **Global** prefix tag, in the **NetworkSpecification** and the **ServerNodeSpecifications** parameter to enable an HPSM connection to the JADE Database service across Windows sessions.

The **HPSM** transport has lower overhead than the **JadeLocal** transport, and is a better fit with the server thread model, as it has fewer thread context switches per request. For details about the server thread model, see "[Server Thread Model](#)", later in this chapter.

On a client node using HPSM, the **Node** class **networkAddress** method returns "**procNNNN**", where the **NNNN** value is the decimal number of the process at the other end of the connection.

Alternatively, use the **server** parameter in a command line to specify the server Universal Resource Identifier (URI) target database and the client-server transport, instead of the **server** and **path** parameters in a command line and the **ServerNodeSpecifications** parameter in the [**JadeClient**] section of the JADE initialization file. For details, see "[Format of the Server URI String](#)", later in this chapter.

JadeLocal Transport

The **JadeLocal** transport between the JADE database and standard clients is implemented by the use of shared memory, global events, and semaphores.

Note The **JadeLocal** transport should be used when a node has one or two processes only.

The following JADE initialization file parameters are required to use the **JadeLocal** transport.

```
[JadeServer]
NetworkSpecification<n>=JadeLocal,enabled|disabled,[Global\]base-name

[JadeClient]
ServerNodeSpecifications=JadeLocal,[Global\]base-name
```

The *base-name* value can have an optional **Local** or **Global** prefix, as described for the HPSM transport, earlier in this chapter.

If the prefix is absent, it defaults to **Local**, which is consistent with running with the least-privileges mode. When running as a standard user, the value of the *base-name* variable is created in the **Local** or session namespace, which means that all JADE programs must be running as the same user logon and also in the same Windows session, to be able to connect to this RPC transport. For example, if the database is installed as a service, all application servers and standard clients wanting to connect to this database via **JadeLocal** transport must also be running as services and under the same user logon.

Note Local intra-machine transport is used only when the transport type is defined as **JadeLocal** or **HPSM** on both the server and client and the network state on the server is defined as **Enabled**.

Alternatively, use the **server** parameter in a command line to specify the server Universal Resource Identifier (URI) target database and the client-server transport, instead of the **server** and **path** parameters in a command line and the **ServerNodeSpecifications** parameter in the [**JadeClient**] section of the JADE initialization file. For details, see "[Format of the Server URI String](#)", in the following section.

Format of the Server URI String

Use the **server** parameter in a command line to specify the server Universal Resource Identifier (URI) target database and the client-server transport, instead of the **server** and **path** parameters in a command line and the **ServerNodeSpecifications** parameter in the [JadeClient] section of the JADE initialization file.

The syntax of the server URI command line parameter is as follows.

```
server=scheme://target-address/environment-UUID[/server-UUID] [?parameters]
```

The *scheme* and *target-address* values specify the client-server transport definition. The environment identity UUID (in display form) specifies the database to which the client node is connecting. This is optionally followed by the database server identity UUID. For details about the database identities, see "Database Identities", in Chapter 3 of the *JADE Database Administration Guide*.

Specify both environment and server identities when you want the client node to connect to a specific SDS secondary database.

The following subsections explain how you can specify the target address for each URI scheme.

File Scheme (Single User)

The format of the single user **File** scheme is as follows.

```
File://database-directory
```

The *database-directory* value specifies the name of the directory where the database server finds the database control file (**_control.dat**). Use this format when running a single user client node; for example:

```
File://c:\jade\system
```

This example is equivalent to **server=SingleUser** and **path=c:\jade\system** in the command line.

TcpIP, TcpIPv4, and TcpIPv6 Schemes

The format of the target address in the **TcpIP**, **TcpIPv4**, and **TcpIPv6** schemes is as follows.

```
host:port-number
```

You can specify the host using a:

- Simple host name; for example, **george**, **server129**, or **localhost**.
- Fully qualified domain name (FQDN); for example, **wilbur.example.com**.
- Dotted decimal IPv4 address; for example, **127.0.0.1**.
- Quadded hexadecimal IPv6 address enclosed in square brackets; for example, **[fe80::bdf1:cbe:6902:7deb]**.

The **TcpIPv4** scheme uses the IPv4 protocol, so quadded hexadecimal IPv6 addresses are not allowed.

The **TcpIPv6** scheme uses the IPv6 protocol, so dotted decimal IPv4 addresses are not allowed.

The *port-number* value is a decimal integer in the range 1 through 65535.

When the host is a simple host name or an FQDN, resolution always returns **TcpIPv6** addresses before **TcpIPv4** addresses. When a specific protocol version is not specified, the first returned address is used.

The following examples show target addresses for the **TcpIP**, **TcpIPv4**, and **TcpIPv6** schemes.

```
server=TcpIP://localhost:6005/48cf13df-bf6d-df11-87e2-2e5925024153
```

```
server=TcpIPv4://host.company.com:6005/48cf13df-bf6d-df11-87e2-2e5925024153?localhostname=aHostName
```

```
server=TcpIPv6://[fe81::6fe:7fff:fe87:bd20]:6005/48cf13df-bf6d-df11-87e2-2e5925024153?localPort=54321
```

```
server=TcpIP://127.0.0.1:6005/48cf13df-bf6d-df11-87e2-2e5925024153/48cf13df-bf6d-df11-87e2-2e5925024153
```

By default, the environment identity specified in the **server** command line parameter of a client shortcut must match the identity of the database server, as shown in the following example.

```
server=TcpIp://localhost:6005/48cf13df-bf6d-df11-87e2-2e5925024153
```

If zeroes can be specified for the environment identity in the **server** command line parameter of a client shortcut, as shown in the following example, set the value of the **AcceptZeroEnvironmentUUID** parameter in the [\[JadeServer\]](#) section of the JADE initialization file to **true**.

```
server=TcpIp://localhost:6005/00000000-0000-0000-0000-000000000000
```

Caution The **AcceptZeroEnvironmentUUID** parameter should not be set to **true** in production databases.

The following optional parameters enable you to specify the client node source address and port.

- **LocalInterface=host**

The *host* value is a simple host name, a fully qualified domain name, or an appropriate IP address. You can use this to select a specific source address when the client machine has more than one network interface.

- **LocalPort=port-number**

The *port-number* value is a decimal integer in the range 1 through 65535. You can use this when the default random source port number cannot be used; for example, when the client and server machines are separated by a firewall, which limits the client source port numbers.

Hybrid Pipe Shared Memory (HPSM) Scheme

In the Hybrid Pipe Shared Memory (**HPSM**) scheme, shared memory is used to establish a connection so the client node must be on the same machine as the server.

The format of the target address is as follows.

```
localhost:base-name
```

The host must be **localhost**. The *base-name* contains up to 60 ASCII graphic characters excluding the forward slash (/), percent (%), and comma (,) characters. When the database server is installed as a Windows service, the *base-name* should be prefixed with **Global**.

The following example shows a target address for the **HPSM** scheme.

```
server=HPSM://localhost:SRCJade-HPSM/48cf13df-bf6d-df11-87e2-2e5925024153
```

JadeLocal Scheme (Shared Memory)

In the **JadeLocal** scheme, shared memory is used to establish a connection so the client node must be on the same machine as the server.

The format of the target address is as follows.

```
localhost:base-name
```

The host must be **localhost**. The *base-name* contains up to 60 ASCII graphic characters excluding the forward slash (/), percent (%), and comma (,) characters. When the database server is installed as a Windows service, the *base-name* should be prefixed with **Global** and the *base-name* value name in the range 1 through 60 characters.

The following example shows a target address for the **JadeLocal** scheme.

```
server=JadeLocal://localhost:SRCJade-SHM/48cf13df-bf6d-df11-87e2-2e5925024153
```

Server Thread Model

The server thread model uses two thread pools, as follows.

- The first pool (short threads) handles request types that have a short execution time (for example, a **getObject** call).
- The second pool (long threads) handles the request types that are expected to have a relatively long execution time.

Both thread pools use a Windows I/O completion port to distribute requests among its threads, thereby reducing the thread context switches in the server process.

The thread pools are managed with parameters in the [**JadeServer**] section of the JADE initialization file, as shown in the following example.

```
[JadeServer]
TransportIdlePollInterval=120000
MinShortThreads=10
MaxShortThreads=100
ConcurrentShortThreads=0
MinLongThreads=5
MaxLongThreads=50
ConcurrentLongThreads=0
```

All transports perform a keep-alive check, whose frequency is controlled by the value of the **TransportIdlePollInterval** parameter.

The number of threads in each pool grows dynamically, starting with the values of the **MinShortThreads** and **MinLongThreads** parameters, up to the values of the **MaxShortThreads** and **MaxLongThreads** parameters, depending on the request arrival rate.

The values of the **ConcurrentShortThreads** and **ConcurrentLongThreads** parameters control the maximum number of threads that the operating system can allow to concurrently process I/O completion packets for each I/O completion port. If the value of these parameters is the recommended value of zero (0), the system allows as many concurrently running threads as there are cores in the system. (For further details, see the Microsoft MSDN **CreateloCompletionPort** function at <http://msdn.microsoft.com>.)

Connecting to JADE Applications from Internet Information Server (IIS)

Your connections from the Internet Information Server (IIS) to JADE applications are via a TCP/IP connection. (For more details, see "[Configuring JadeHttp for Remote Connections](#)", later in this chapter.)

To implement a TCP/IP connection from IIS to JADE applications, define a section within the `jadehttp.ini` file for each application, with the **ApplicationType** parameter and unique multiple **TcpPort[n]**, **MinInUse[n]**, **MaxInUse[n]**, **TcpConnection[n]**, **CloseDelay[n]**, and **ConnectionGroup[n]** parameters within each `[application-name]` section. Set the **ApplicationType** parameter in each `[application-name]` section to **RestServices**, **WebEnabledForms**, **WebServices**, or **HtmlDocuments**. The following is an example of these parameters.

```
[HtmlCompany]
ApplicationType = HtmlDocuments
TcpConnection  = Host1a
TcpPort        = 22000
MinInUse       = 2
MaxInUse       = 10
CloseDelay     = 600
TcpConnection2 = Host2a
TcpPort2       = 22001
MinInUse2      = 2
MaxInUse2      = 10
CloseDelay2    = 600
```

Connecting to JADE Applications from an Apache HTTP Server

Your connections from the Apache HTTP Server to JADE applications can be via a TCP/IP connection only. The design and configuration of the `mod_jadehttp` module fully conforms to Apache HTTP Server 2.4 module usage and configuration practices.

You can obtain more information about the Apache Software Foundation from one of the following Web sites.

<http://www.apache.org>

<http://httpd.apache.org>

JADE supports the Apache HTTP Server by supplying `mod_jadehttp`. Only **JadeInternetTCPIPConnection** class TCP/IP communications are supported for all versions of `mod_jadehttp`, regardless of the operating system; that is, TCP/IP connections only are used for connections to JADE applications running from the Apache HTTP Server. For details, see "[Using the mod_jadehttp Module](#)", in the following subsection.

The `mod_jadehttp` library module supplied by JADE for the Apache HTTP Server implements support for the following Multi-Processing Modules (MPMs). The selection of the default MPM is selected based on the operating system on which the Apache server is running; that is, `mpm_winnt` is the default value for Microsoft-based operating systems.

If you build the Apache server from source code, you can build and select whichever MPM you want to use, on the operating system of your choice.

Some relevant MPMs with respect to JADE and the `mod_jadehttp` library are listed in the following table.

Multi-Processing Module (MPM)	Implements a ...
<code>mpm_winnt</code>	Multiple-threaded single process Web server
<code>prefork</code>	Non-threaded, pre-forking Web server
<code>worker</code>	Hybrid multiple-threaded multiple-process Web server

The **mod_jadehttp** module ensures that the same destination IP address and port number combination are used for a specific logical connection, by using the hidden fields that both the **jadehttp** and the **mod_jadehttp** libraries insert into the HTML data.

» To install the mod_jadehttp module

- Copy the **mod_jadehttp.so** file into the **modules** directory of your Apache HTTP Server.

Notes The name **mod_jadehttp.so** applies to all operating systems.

Ensure that you use the correct operating system binary.

Apache and the HTTP generally use UTF-8 as the encoding scheme for Unicode data on the Web. As **mod_jadehttp** currently does not allow for this and it passes the data directly to JADE, only ANSI data can be read from or written to the [JadeInternetTCPIPConnection](#) object.

For details about configuring the Apache HTTP Server, see "[Configuring Apache for Remote Connections](#)", later in this chapter.

Using the mod_jadehttp Module

JADE includes **mod_jadehttp32.so** and **mod_jadehttp64.so**, for the 32-bit and 64-bit version of Apache 2.4.10, respectively.

» To use the mod_jadehttp module

1. Ensure that you are running Apache 2.4.10 or a higher 2.4.*n* version.
2. Determine whether 32-bit or 64-bit Apache is installed. (If the operating system installation is a 64-bit version, it is most likely that Apache is also the 64-bit version.)
3. Load the correct **mod_jadehttp** module into Apache. Note that path names in following examples may differ from those in your environment.

For 32-bit versions of Apache:

```
LoadModule jadehttp_module modules/mod_jadehttp32.so
```

For 64-bit versions of Apache:

```
LoadModule jadehttp_module modules/mod_jadehttp64.so
```

Configuring Your JADE Software

The JADE initialization file enables you to configure JADE to your requirements. For details, see "[JADE Initialization File](#)", in the *JADE Initialization File Reference*.

The physical database layer or database engine of the JADE Object Manager can use the information stored in the [\[PersistentDb\]](#) and [\[TransientDb\]](#) sections of the JADE initialization file to configure itself to meet defined performance or resource constraints, or user preferences.

Note In a multiple-database environment, each database can have its own unique JADE initialization file and configuration parameters.

You can also:

- Set options to specify your user configuration in the JADE command line, for use when running a JADE application from outside the development environment. For details, see "[JADE Configurations under Windows](#)", in Chapter 1, and "[Format of the Server URI String](#)", earlier in this chapter.
- Specify your installation global preferences that apply to all JADE Browser and Painter windows for your JADE development environment work sessions in the installed JADE release. For details, see "[Specifying Your Administration Options](#)", later in this chapter.
- Specify options in the `jadehttp.ini` file for use when accessing JADE applications from the Internet Information Server (IIS). For details, see "[Configuring JadeHttp for Remote Connections](#)", later in this chapter.
- Specify options in the `mod_jadehttp` module, for use when accessing JADE applications from the Apache HTTP Server. For details, see "[Configuring Apache for Remote Connections](#)", later in this chapter.

Configuring the Internet Protocol Version

JADE supports Internet Protocol Version 4 (IPv4) and Internet Protocol Version 6 (IPv6).

These transport protocols are used in the following areas of JADE.

- Remote Procedure Call (RPC), between database server and nodes
- Thin client, between the application server and presentation clients
- Synchronized Database Service (SDS), between SDS nodes
- Web, between the node and the Web server add-in (that is, `jadehttp.dll` or `mod_jadehttp.so`)
- User code in your application that uses the `TcplpConnection` class
- ODBC, between the thin client and server

The following JADE initialization file parameter values refer to networking.

- `[JadeServer]` section and `NetworkSpecification` parameter
- `[ConnectionParams]` section `NetworkSpecification` and `ServerNodeSpecifications` parameters
- `[JadeClient]` section `ProxyHost` and `ServerNodeSpecifications` parameters
- `[JadeAppServer]` section `AppServer` parameter
- `[JadeThinClient]` section `AppServer` and `SSLProxyHost` parameters
- `[JadeOdbcServer]` section `ListenerHostName` and `ListenPort` parameters

The system administrator should review the following host name and IP address values of the following properties for potential changes, to enable the IPv6 feature. JADE developers who expect a deployed system to support the IPv6 feature should review their code that accesses these properties, as these properties can now return different values and break assumptions that you may have previously made.

The most-common change is that IP addresses will have a *dot quad number* format (for example, 192.168.254.254) and be a maximum of 16 characters. For details, see "[Limits and Defaults](#)", later in this chapter.

- `TcplpConnection::localInterface`
- `TcplpConnection::localIpAddress`
- `TcplpConnection::remoteIpAddress`

- `TcpIpConnection::remoteName`
- `TcpIpConnection::protocolFamily`
- `Connection::name`
- `JadeTcpIpProxy::host`
- `JadeMultiWorkerTcpTransport::listenHostname`
- `JadeMultiWorkerTcpConnection::listenHostname`
- `JadeMultiWorkerTcpConnection::localAddress`
- `JadeMultiWorkerTcpConnection::remoteAddress`
- `JadeMultiWorkerTcpConnection::getFullName`
- `JadeMultiWorkerTcpConnection::getLocalHostname`
- `JadeMultiWorkerTcpConnection::getRemoteHostname`
- `Process::networkAddress`
- `Node::getComputerName`
- `Node::networkAddress`

RPC, Database, and Node Configuration

This section covers the area of behavior and configuration between the database server (including SDS environments) and client nodes.

Configuring the Database Server

Configure the database server by specifying the following values for the [NetworkSpecification](#) parameter in the [\[JadeServer\]](#) section of the JADE initialization file, as follows.

```
NetworkSpecification<specification-number> = transport-
type,enabled|disabled,listener-port[,interface]
```

The values for the *transport-type* variable relevant to this feature can be **TcpIP**, **TcpIPv4**, or **TcpIPv6**. The *transport-type* literal value is case-insensitive.

The **TcpIP** value is a synonym for **TcpIPv4**. **TcpIPv4** provides IP version 4 connections only. **TcpIPv6** provides IP version 6 connections only. If you want the server to support both network protocols, you must define a network specification for each protocol.

You can specify the *interface* value as a host name or an IP address. If you use an IP address, the address must be in an appropriate format for the specified *transport-type* value.

Configuring the Client Node

Configure the client node by:

- Specifying the following values for the [ServerNodeSpecifications](#) parameter in the [\[JadeClient\]](#) section of the JADE initialization file.

```
ServerNodeSpecifications = transport-type,remote-host,remote-port
[,local-interface[,local-port]]
```

The values for *transport-type* variable relevant to this feature can be **TcpIP**, **TcpIPv4**, **TcpIPv6**, or **TcpIPAny**. The *transport-type* literal value is case-insensitive. The **TcpIP** value is a synonym for **TcpIPAny**. **TcpIPv4** provides IP version 4 connections only. **TcpIPv6** provides IP version 6 connections only. The **TcpIPAny** value supports IP version 6 or IP version 4 connections.

You can specify the *remote-host* and *local-interface* values as a host name or an IP address. If you use an IP address, the address must be in an appropriate format for the specified *transport type* value. If you specify a host name, all DNS-provided addresses will be attempted. For the **TcpIPAny** transport type, the client will first attempt to connect via IP version 6 and then IP version 4 protocol on the provided IP addresses. Each connection failure will be logged, and the next available combination tried.

- Using the **server** parameter in a command line to specify the server Universal Resource Identifier (URI) target database and the client-server transport, instead of the **server** and **path** parameters in a command line and the **ServerNodeSpecifications** parameter in the [JadeClient] section of the JADE initialization file. For details, see "Format of the Server URI String", earlier in this chapter.

Configuring SDS Connections

Configure SDS connections by specifying the following values for the **NetworkSpecification** and **ServerNodeSpecifications** parameters in the [ConnectionParams] section of the JADE initialization file.

```
NetworkSpecification<specification-number> = transport-
type,enabled|disabled,listener-port[,interface]
```

```
ServerNodeSpecifications = transport-type,remote-host,remote-port[,local-interface
[,local-port]]
```

Both the server side (specified in the **NetworkSpecification** parameter) and the client side (specified in the **ServerNodeSpecifications** parameter) follow the same behavior and rules documented for the database server and client node RPC configurations in the previous sections.

Application Server and Thin Client Configuration

This section covers the area of behavior and configuration between the application server and the presentation client nodes.

Configuring the Application Server

Configure the application server by specifying the following values for the **AppServer** parameter in the [JadeAppServer] section of the JADE initialization file, as follows.

```
AppServer = [transport-type,]interface
```

The values for the *transport-type* variable relevant to this feature can be **TcpIP**, **TcpIPv4**, **TcpIPv6**, or **TcpIPAny**. The *transport-type* literal value is case-insensitive.

If you do not specify a *transport-type*, the default value is **TcpIP**, which is a synonym for **TcpIPv4**. **TcpIPv4** provides IP version 4 connections only. **TcpIPv6** provides IP version 6 connections only. **TcpIPAny** supports IP version 6 or IP version 4 connections. Depending on your requirements, you can configure a single application server to use **TcpIPAny**, or you can set up two application servers so that one supports **TcpIPv4** and the other **TcpIPv6**.

You can specify the *interface* value as a host name or an IP address. If you use an IP address, the address must be in an appropriate format for the selected *transport-type* value.

Because of the way that JADE parses the command line, enclose the parameter values in quote marks if you specify **ApplicationServer="transport-type,interface"** on the command line.

Configuring a Presentation Client

Configure a presentation client by specifying the following values for the **AppServer** and **SSLProxyHost** parameters in the [**JadeThinClient**] section of the JADE initialization file, as follows.

```
AppServer = [transport-type,]interface
SSLProxyHost = interface
```

The values for the *transport-type* variable of the **AppServer** parameter relevant to this feature can be **TcpIP**, **TcpIPv4**, **TcpIPv6**, or **TcpIPAny**. The *transport-type* literal value is case-insensitive.

If you do not specify a *transport-type*, the default value is **TcpIP**, which is a synonym for **TcpIPAny**. **TcpIPv4** provides IP version 4 connections only. **TcpIPv6** provides IP version 6 connections only. **TcpIPAny** supports IP version 6 or IP version 4 connections.

You can specify the *interface* value as a host name or an IP address. If you use an IP address, the address must be in an appropriate format for the selected *transport-type* value. If you specify a host name, all DNS-provided addresses will be attempted. For the **TcpIPAny** transport type, the presentation client will first attempt to connect via IP version 6 and then IP version 4 protocol on the provided IP addresses. Each connection failure will be logged, and the next available combination tried.

Because of the way that JADE parses the command line, enclose the parameter values in quote marks if you specify **ApplicationServer="transport-type,interface"** on the command line.

If SSL has been enabled and the presentation client needs to connect to the application server via a proxy host, the presentation client will attempt to connect to the proxy server using the same protocol (*transport-type*) as that specified in the **ApplicationServer** parameter configuration. How the proxy host handles TCP/IP version 6 is dependent on the proxy host implementation.

The areas to check and to test with the proxy host are as follows.

1. Will it accept an IP version 6 connection?
2. What protocol will it use between the proxy and the application server?

TcpIpConnection Class

This section covers the area of behavior and configuration in using JADE RootSchema-based networking classes.

The **TcpIpConnection** class provides the virtual **protocolFamily** property, which is an Integer value. The values that can be assigned to this property are the new **TcpIpConnection** class constants listed in the following table.

Class Constant	Integer Value
ProtocolFamilyTcpIPv4	0
ProtocolFamilyTcpIPv6	1
ProtocolFamilyTcpIPAny	-1

If you do not change your code, your existing code runs using TCP/IP version 4 only.

Note The **JadeTcpIpProxy** class works only with the TCP/IP version 4 protocol.

Other User Networking Areas

This section contains other areas of your network that may be affected by this feature.

The **TcpConnection** parameter in the **jadehttp.ini** file specifies a host or IP address to which to connect.

If you specify a host name, all DNS-provided address will be attempted. Both the **TcpIPv6** and **TcpIPv4** protocols will be attempted on the provided IP addresses. Each connection failure will be logged, and the next available combination tried.

Limits and Defaults

Your user code must allow for longer network addresses and host names.

A fully qualified hostname can be up to 255 characters, with each label being up to 63 characters (for details, see the RFC2181 clarification to the DNS specification). However, the underlying C++ code allows for 1,025, so allow for a host name of 1,024, to make your code safe. A fully defined IPv6 address, including port number, can be up to 65 characters.

The following is taken from a Microsoft header file, and agrees with other Internet descriptions.

```
// The totals are derived from the following data:  
// 15: Ipv4 address  
// 45: Ipv6 address including embedded Ipv4 address  
// 11: Scope Id  
// 2: Brackets around Ipv6 address when port is present  
// 6: Port (including colon)  
// 1: Terminating null byte  
//  
#define INET_ADDRSTRLEN 22  
#define INET6_ADDRSTRLEN 65
```

Configuring JadeHttp for Remote Connections

The **jadehttp** library module can handle multiple TCP/IP address connections to the same application, which allows the Web server to connect to multiple copies of the same JADE application on multiple hosts. For details, see "[[application-name](#)] Section", later in this chapter. To handle the transfer of large files from a user's browser to JADE for **JadeInternetTCPIPConnection** class connections, data is read in small pieces and written into a temporary file as it goes.

If the **Firewall** parameter in the [[Jadehttp Files](#)] section of the JadeHttp initialization file or the **Firewall** configuration directive in the JADE **mod_jadehttp** module and the **Firewall** parameter in the [[WebOptions](#)] section of the JADE initialization file are set to **true**, the contents of the temporary file is sent (in pieces) to JADE when the entire data stream has been received. JADE then reads those pieces and writes the file contents as it goes (therefore avoiding large memory allocations). This is transparent if the **Firewall** parameter or directive is set to **false** or if it is set to **true** and one of the following applies.

- The **FileTransferDirectory** parameter in the [[Jadehttp Files](#)] section of the **jadehttp.ini** file or the **FileTransferDirectory** configuration directive in the JADE **mod_jadehttp** module is set to **default** or to a valid directory (used to hold temporary file contents as the data is read from the Internet).
- The standard **readPipeCallback** method of the **JadeInternetTCPIPConnection** class is used to read the data.

Note The firewall must be enabled at both ends of the connection (that is, if you are uploading images from another machine for a JADE Web-enabled form over a TCP/IP connection, the **Firewall** parameter in the [[Jadehttp Files](#)] section of the JadeHttp initialization file or the **Firewall** configuration directive in the JADE **mod_jadehttp** module and the **Firewall** parameter in the [[WebOptions](#)] section of the JADE initialization file must both be set to **true**).

The **jadehttp.ini** file is located in the virtual directory (that is, the IIS server location). Each virtual directory has its own **jadehttp.ini** file. (For details about the paths, see "[[Jadehttp Files](#)] Section", later in this chapter.)

The `JadeHttp` initialization file or JADE `mod_jadehttp` module is read-only when the first request for an application is received. If you update a parameter value in this file, you must therefore stop the Internet service and then restart it.

Firewall for the JADE Internet Environment

As the `JadeHttp` library or the JADE `mod_jadehttp` module can communicate via a TCP/IP connection to a different workstation running the JADE application, you can ensure that the JADE environment is entirely behind the firewall. In the default implementation of the JADE Internet environment, the JADE application writes image files directly into the virtual directory for subsequent Web browser access.

Files transferred by a Web browser to the `JadeHttp` library are written into a directory for access by the JADE application.

Use of a firewall requires that there are no network directory services running between the Web browser and JADE environments.

The only available links are TCP/IP connections. JADE applications do not write files directly into the virtual directory outside the firewall. Instead, the files must be passed via the TCP/IP connection to the `JadeHttp` library, which creates the file in the virtual directory. Similarly, files arriving at the `JadeHttp` library from a Web browser are passed to the JADE application via the TCP/IP connection.

The JADE application writes these files into the JADE Web application directory.

Files Created by the JADE Application

Use the `Firewall` parameter in the [`Jadehttp Files`] section of the `JadeHttp` initialization file or the `Firewall` configuration directive in the JADE `mod_jadehttp` module to control whether JADE uses this facility for its automatic HyperText Markup Language (HTML) generation. When this parameter or directive is set to the default value of `false`, files are written directly to the virtual directory by JADE.

When you set this parameter or directive to `true` and the `Firewall` parameter in the [`WebOptions`] section of the JADE initialization file is also set to `true`, files are transferred to the `JadeHttp` library via the TCP/IP connection before being passed to the virtual directory.

The `JadeWebServiceProvider` and `WebSession` classes provide a `createVirtualDirectoryFile` method, which enables you to pass files created by a JADE application to the `JadeHttp` library.

The `createVirtualDirectoryFile` method has the following signature:

```
createVirtualDirectoryFile(fileName:      String;
                          fileContents: Binary;
                          retain:       Boolean): Integer;
```

The `createVirtualDirectoryFile` method parameters are listed in the following table.

Parameter	Description
<code>fileName</code>	Name of the file to be created in the virtual directory
<code>fileContents</code>	Binary holding the file contents
<code>retain</code>	Creates read-only files when set to <code>true</code> or standard files when set to <code>false</code>

The `JadeHttp` library creates the specified file in the directory (the virtual directory visible to Web browsers) in which the library is running. This method returns zero (0) if the method successfully formats a request to the `JadeHttp` library or it returns the non-zero Windows error code indicating the failure to create the file.

The image files must be passed before the final reply to the Web request is returned.

This process is transparent to you if your application is using the standard JADE generated Internet facility. However, if your application logic does additional file generation of its own, you must call the [JadeWebServiceProvider](#) or [WebSession](#) class `createVirtualDirectoryFile` method.

For Web services applications, the virtual directory parameter *must* be specified and the `fileName` parameter contains only the file name. When an application transfers files to the `jadehttp` library by using the `createVirtualDirectoryFile` method for non-Web services applications, the directory that is used is determined as follows.

- If the file name specified in the `fileName` parameter includes a directory, the file is written into that directory.
- If the file name does not include a directory and the application's section of the `jadehttp.ini` file or the JADE `mod_ jadehttp` module contains a directory value for the [VirtualDirectory](#) parameter or [PhysicalDirectory](#) directive, respectively, the files are written into that directory.

If neither the file name nor the `[application-name]` section of the `jadehttp.ini` file or the directive [ApplicationType](#) in the JADE `mod_ jadehttp` module contains a directory, the files are written into the same directory as the `jadehttp` library module. (This enables you to control directory permissions so that the directory containing the `jadehttp` library module does not need to have read and write access.)

Use the [JadeWebServiceProvider](#) or [WebSession](#) class `isVDFilePresent` method to return whether the requested file specified in the `fileName` parameter of the method is present on the Web server side of the firewall when using the JADE Web interface via the `jadehttp` library file. This method sends a message to the `jadehttp` library file to perform this action. If the specified file name does not have a directory part, the current virtual directory defined in the [VirtualDirectory](#) parameter in the `JadeHttp.ini` file or the [PhysicalDirectory](#) directive in the JADE `mod_ jadehttp` module for the application is used. The file specified in the `fileName` parameter of the `isVDFilePresent` method is used if the file name has a directory part.

Call the [JadeWebServiceProvider](#) or [WebSession](#) class `deleteVirtualDirectoryFile` method to delete files that are in the virtual directory (that is, the directory specified by the value of the [VirtualDirectory](#) parameter in the `JadeHttp.ini` file or the [PhysicalDirectory](#) directive in the JADE `mod_ jadehttp` module).

The `deleteVirtualDirectoryFile` method parameters are listed in the following table.

Parameter	Description
<code>fileName</code>	Name of the file to be deleted from the virtual directory
<code>deleteIfReadOnly</code>	Deletes files marked as read-only when set to true

This method returns zero (0) if the file deletion is successful or it returns a non-zero error code if the deletion fails.

Notes If your applications are not using the standard JADE generated Internet facility, you need to set the [Firewall](#) parameter in the [\[Jadehttp Files\]](#) section of the `jadehttp.ini` file or the [Firewall](#) configuration directive in the JADE `mod_ jadehttp` module and the [\[WebOptions\]](#) section of the JADE initialization file to **true** and call the [JadeWebServiceProvider](#) or [WebSession](#) class `createVirtualDirectoryFile` method *only* if you require firewall separation. If you do not require firewall separation, JADE creates image files directly into the virtual directory and bypasses the `JadeHttp` library.

The file cleanup process that is started when the `jadehttp.ini` file [Firewall](#) parameter or the JADE `mod_ jadehttp` module [Firewall](#) configuration directive is set to **true** deletes only files that are *not* read-only and which are of type `.jpg`, `.png`, or `.gif`. You should therefore make all other files in this directory that you want to retain read-only, by setting the `retain` parameter to **true**.

Files Transferred from the Web Browser

Use the **Firewall** parameter in the [Jadehttp Files] section of the **jadehttp.ini** file or the **Firewall** configuration directive in the JADE **mod_jadehttp** module to control whether firewall separation is used when transferring files to JADE from Web browsers. When the **Firewall** parameter or directive is set to **false**, the default mechanism is used.

When you set the **Firewall** parameter or directive to **true** and the **Firewall** parameter in the [WebOptions] section of the JADE initialization file is also set to **true**, files are transferred to the JADE application over the TCP/IP connection and each file transferred from a Web browser is sent to the JADE application as a separate message. Your JADE application must distinguish this message from a normal Web browser request and store the transferred file.

The **JadeHttp** library reads data in small pieces and writes it into a temporary file as it goes. The contents of the temporary file are sent (in pieces) when the entire data stream is received. JADE then reads those pieces and writes the file contents as it goes, which avoids large memory allocations. For details, see "[Configuring JadeHttp for Remote Connections](#)", earlier in this section.

For details about the location of files, see "[Controlling the Location of Files Uploaded via a Web Application](#)", later in this chapter.

The message sent through the firewall is formatted as follows.

File Component	Description
Header	TRF , followed by a null
File name	Name of the file that is to be created, followed by a null
File contents	Binary image

The handling of this message is placed in the **Connection** class **readPipeCallback** method before the rest of the general processing. (Note that no reply should be sent for this message.) When the JADE application receives the Web browser request, it stores the file in the specified Web application directory.

Note There is no cleanup method invoked if your user logic does not remove the files. Your application should delete these files when processing on them is complete.

When a file is transferred to JADE from a Web browser by using the default connection mechanism, the text for the text box that generated the transfer is changed by the **JadeHttp** library to:

```
<original-file-name>;<temporary-file-name-and-path>
```

If you have set the **Firewall** parameter in the [Jadehttp Files] section in the **jadehttp.ini** file or the **Firewall** configuration directive in the JADE **mod_jadehttp** module and the **Firewall** parameter in the [WebOptions] section of the JADE initialization file to **true**, the text is set to:

```
<original-file-name>;<temporary-file-name>
```

Your application logic that accesses the file must append the Web application directory to the temporary file name to form the actual path. (To get the name of the Web application directory, call the **Application** class **webApplicationDirectory** method, which returns a string containing the directory name.)

Internal Housekeeping of the Virtual Directory

When JADE sends a file to the **JadeHttp** library, any file that is not to be retained is created as a standard file of type **.jpg**, **.png**, or **.gif** when the **jadehttp.ini** file **Firewall** parameter or the JADE **mod_jadehttp** module **Firewall** configuration directive, the **Firewall** parameter in the **[WebOptions]** section of the JADE initialization file, and the **retain** parameter in the **JadeWebServiceProvider** or **WebSession** class **createVirtualDirectoryFile** method are set to **true**. Files that are to be retained are created as read-only files.

Call the **JadeWebServiceProvider** or **WebSession** class **deleteVirtualDirectoryFile** method to delete virtual directory files (that is, the directory specified by the value of the **VirtualDirectory** parameter in the **jadehttp.ini** file or the **PhysicalDirectory** configuration directive in the JADE **mod_jadehttp** module).

By default, JADE initiates a separate thread to clean up files in the virtual directory when **JadeHttp** is started up if the **Firewall** parameter in the **[Jadehttp Files]** section of the **JadeHttp** initialization file or the **Firewall** configuration directive in the JADE **mod_jadehttp** module is set to **true**. Every hour this thread removes any standard files of type **.jpg**, **.png**, or **.gif** that are more than 12 hours old, by default. (As the **JadeHttp** library has no life of its own until a message is received, this thread is initiated only after the first Web browser message is received.)

Alternatively, set the value of the **PurgeDirectoryRule** parameter in the **[application-name]** section of the **jadehttp.ini** file or the **PurgeDirectoryRule** configuration directive in the JADE **mod_jadehttp** module to **AllWritable** if you want to purge all files in the virtual directory that are not read-only. The default value of **Default** for this parameter removes any standard files of type **.jpg**, **.png**, or **.gif** that are more than 12 hours old. If you want to specify the length of time since a read-only file was last modified before it is purged from the defined virtual directory for that application, specify the required value in the **PurgeFileAge** parameter.

Controlling the Location of Files Uploaded via a Web Application

If your JADE application accepts file input in text boxes on a Web page (by using the **webInputType** property of a **TextBox** control with the **Web_InputType_File** setting to upload a file from a Web session), you can use the **FileTransferDirectory** parameter in the **[Jadehttp Files]** section of the **jadehttp.ini** file to specify the directory to which the file is written.

This parameter controls the directory in which any files transferred using the HTML **InputType=file** option are placed. (This parameter applies only when the **Firewall** parameter in the **[Jadehttp Files]** section of the **jadehttp.ini** file or the **Firewall** configuration directive in the JADE **mod_jadehttp** module is set to **false**.) By default, any transferred files are placed in the same directory as the **jadehttp** library file or the JADE **mod_jadehttp** module.

The format of the **text** property value of the **TextBox** control is as follows.

```
<source-file-name>;<destination-file-path><destination-file-name>
```

The *source-file-name* value is the name (excluding the path) of the originating file on the client workstation from which the file was loaded (that is, the workstation that is running the Web browser). A semicolon character (;) separates this and the *destination-file-path* and *destination-file-name* values, which are the full path to which the file is written (uploaded) and the name of that file; for example:

```
UsefulStuff.doc;d:\jade\bin\txf188.tmp
```

In this example, accessing the **txf188.tmp** file in the specified directory opens a document file that contains the information in the **UsefulStuff.doc** file uploaded via the Web browser.

To provide increased security for applications running in HTML thin client mode, a text file input by using the `TextBox` class `webInputType` property with a value of `Web_InputType_File` must be processed in the event that resulted in the file upload occurring (for example, in the `click` event method of a `Completed` button). In addition, set the value of the `Trace` parameter in the `[Jadehttp Logging]` section of the `jadehttp.ini` file to `false` to suppress logging completely. When the value of this parameter is set to `true`, logged messages acknowledge only that a message has been received or sent, because it is not possible to distinguish what is sensitive data and what is not. Setting this parameter to `true` does *not* include any of the text sent or received from the client, as this text could contain personal information, passwords, credit card details, and so on.

Caution To prevent malicious use of files uploaded to Web-enabled applications, the files are removed as soon as the event that resulted in their upload has completed. You should therefore process the file immediately or move it into a directory that is not available from the Web if you require that file for future processing.

[application-name] Section

To ensure that an application specified in a Web browser cannot cause an attachment to a non-JADE environment, you must specify the name of the Web application to which users can connect, by defining a unique `[application-name]` section for each Web-enabled JADE application.

IIS attempts to attach only to the applications whose names are specified as section names in the `jadehttp.ini` file.

Note The `jadehttp` library module can handle connections for up to 50 different hosts (that is, you can define up to 50 unique `TcpPort[n]`, `MinInUse[n]`, `MaxInUse[n]`, `TcpConnection[n]`, `CloseDelay[n]`, and `ConnectionGroup[n]` parameters within each `[application-name]` section).

The `[application-name]` section of the `jadehttp.ini` file contains parameters that define TCP/IP connections that are used instead of the default named pipe connections. For more details and the application requirements for TCP/IP connections, see "[Connecting to JADE Applications from Internet Information Server \(IIS\)](#)", earlier in this chapter.

To specify that TCP/IP connections are used to connect to JADE release 7.1 applications from IIS, you must define a section with a unique name within the `jadehttp.ini` file for each application, with the `ApplicationType` parameter and unique multiple `TcpPort[n]`, `MinInUse[n]`, `MaxInUse[n]`, `TcpConnection[n]`, `CloseDelay[n]`, and `ConnectionGroup[n]` parameters within each `[application-name]` section. Set the `ApplicationType` parameter in each `[application-name]` section to `RestServices`, `WebEnabledForms`, `WebServices`, or `HtmlDocuments`.

The `[application-name]` section can contain the following parameters.

ApplicationType

Value Type String

Default Not specified

Purpose

The `ApplicationType` parameter, which is required in all `[application-name]` sections of the `jadehttp.ini` file, specifies the type of application that will be supported and how the interfaces to JADE function. The valid parameter values are listed in the following table.

Parameter Value	Description
RestServices	Representational State Transfer (REST) lightweight Web service that embraces HyperText Transfer Protocol (HTTP) through Extensible Markup Language (XML) or JavaScript Object Notation (JSON) messages instead of SOAP.

Parameter Value	Description
WebEnabledForms	Web-enabled forms. This application type results in all requests from a user being directed to the same JADE application copy during the user's session. JadeHttp no longer inserts the tags into the HTML output; the JADE software now performs this function. The JADE side uses the multi-worker TCP facility to perform routing and queuing.
WebServices	Web service operation, where user requests are sent to any available connection. The JADE side uses the multi-worker TCP facility to perform routing and queuing.
HtmlDocuments	HTML documents operation where user requests are sent to any available connection. The JADE side uses the multi-worker TCP facility to perform routing and queuing.

CloseDelay[n]

Value Type Integer (*number-of-seconds*)

Default Not specified

Purpose

When the current number of in-use connections for the TCP/IP specified in the **TcpPort[n]** parameter exceeds the value of the **MinInUse[n]** parameter, the **CloseDelay[n]** parameter indicates how many seconds before the extra connections are closed after they become inactive.

This value is used only when the value of the **ApplicationType** parameter is set to **RestServices**, **WebEnabledForms**, **WebServices**, or **HtmlDocuments**.

ConnectionGroup[n]

Value Type String

Default Not specified

Purpose

The **ConnectionGroup[n]** parameter specifies the name of the connection group associated with the value of the **TcpPort[n]** parameter (that is, the TCP/IP port to be used for the connection).

The connection group is the unique name that is used by applications of type **WebEnabledForms** to identify the TCP/IP port (the value of the **TcpPort[n]** parameter) to which a user request is to be sent.

Note

If you do not specify this parameter with a unique connection group name, this process does not function correctly.

MaxInUse[n]

Value Type Integer

Default Not specified

Purpose

The **MaxInUse[n]** parameter specifies the maximum number of connections that can be opened for the corresponding value of the **TcpPort[n]** parameter only when the value of the **ApplicationType** parameter is set to **RestServices**, **WebEnabledForms**, **WebServices**, or **HtmlDocuments**.

The **MaxInUse** parameter with no specified suffix is the limit for a **ConnectionGroup** associated with an entry with the **TcpConnection** parameter; it is *not* a global limit.

The **MaxInUse[n]** parameter defines the limit of outstanding requests for a single connection group; that is, the sum of queued and active requests. The total number of outstanding requests for a Web application is the sum of the **MaxInUse[n]** suffix values for all of the connection groups specified for that application.

Note

The value of the **MaxInUse** parameter is forced to be equal to or greater than the value of the **MinInUse** parameter.

MaxMessageSize

Value Type Integer

Default 1000000 bytes

Purpose

The **MaxMessageSize** parameter specifies the maximum size allowed for a single-part Web message (that is, a single stream of data with minimal formatting). If the size of a single-part message exceeds the specified value of this parameter, the request is rejected and the following message is displayed to the user.

```
The size of the input data exceeds the limit permitted for this application and has been rejected.
```

Note

Multiple-part formatted Web messages are not limited in size (each message is made up of a series of sections that are specifically formatted).

MessageTimeout

Value Type Integer (*seconds*)

Default 300

Purpose

The **MessageTimeout** parameter specifies the maximum number of seconds that the **JadeHttp.dll** library waits for a reply from a JADE system before sending a failure message to the requesting Web browser.

Hints

This parameter enables you to test the effects of unexpectedly long request processing without having to wait the default five minutes for each test.

When Web-enabled applications are all busy, you can control the time that a Web browser window shows no action before returning the *Service unavailable* response.

MinInUse[n]

Value Type Integer

Default Not specified

Purpose

The **MinInUse[n]** parameter specifies the minimum number of connections that can be opened for the corresponding value of the **TcpPort[n]** parameter only when the value of the **ApplicationType** parameter is set to **RestServices**, **WebEnabledForms**, **WebServices**, or **HtmlDocuments**.

The default minimum number of connections is **1**.

MinMessageSize

Value Type Integer

Default 10 bytes

Purpose

The **MinMessageSize** parameter specifies the minimum size allowed for a Web message received from JADE using the **WebSession** class **reply** method to send HTML string Web requests back to the client node.

The minimum value is **1** byte, the maximum value **1024** bytes, and the default value **10** bytes.

This value is read the first time the application specified in the `[application-name]` section is accessed after **jadehttp.dll** has been loaded by Internet Information Server (IIS).

PurgeDirectoryRule

Value Type String

Default Default

Purpose

The **PurgeDirectoryRule** parameter specifies when files that are not read-only in the virtual directory are purged. The default value of **Default** for this parameter removes any standard files of type **.jpg**, **.png**, or **.gif** that are more than 12 hours old. Specify a value of **AllWritable** if you want to purge all files in the virtual directory that are not read-only.

PurgeFileAge

Value Type *time-unit[D|H|M]*

Default 12H

Purpose

The **PurgeFileAge** parameter specifies the length of time since a read-only file was last modified before it is purged from the defined virtual directory for that application; for example, **PurgeFileAge=7M**.

The parameter value is a time-unit numeric, optionally followed by a modifier **D** (days), **H** (hours), or **M** (minutes). The **D** multiplier multiplies by 86,400; the **H** multiplier multiplies by 3,600; the **M** multiplier multiplies by 60; and all other time-unit values are treated as seconds. Specify zero (**0**) if you want to turn off the purging of the physical directory.

The minimum time-unit value that you can specify is **30** seconds; the maximum value is **365D** (days). Values outside this range are forced to their respective limits.

This parameter applies only if the **VirtualDirectory** parameter has a specified value, and only files that match the **PurgeDirectoryRule** parameter criteria are considered (that is, all non-read-only files or by default, standard files of type **.jpg**, **.png**, or **.gif** that are more than the specified age).

TcpConnection[n]

Value Type Integer (*tcp-address*)

Default Not specified

Purpose

The **TcpConnection[n]** parameter specifies the unique valid TCP/IP address of the port to connect to on the server (remote) node, to enable Web client nodes to connect to the specified server node across the network through a TCP/IP connection.

TcpPort[n]

Value Type Integer (*tcp-port-number*)

Default Not specified

Purpose

The **TcpPort[n]** parameter specifies the TCP/IP port number to be used for the connection specified in the corresponding **TcpConnection[n]** parameter for applications of type **WebEnabledForms**, **WebServices**, and **HtmlDocuments**.

VirtualDirectory

Value Type String (*virtual-directory-name*)

Default Not specified

Purpose

The **VirtualDirectory** parameter enables you to specify a string containing the name of the virtual directory for the HTML-enabled application.

Hints

The value specified for this parameter is used if the **fileName** parameter value of the **JadeWebServiceProvider** or **WebSession** class **createVirtualDirectoryFile** method does not include a directory. If neither this parameter nor the file name in the **createVirtualDirectoryFile** method contains a directory, the files are written into the same directory as the **jadehttp** library module.

This parameter enables you to control virtual directory permissions so that the directory containing the **jadehttp** library module does not need to have read and write access.

For details about retaining files passed to the **jadehttp** library, see "[Firewall for the JADE Internet Environment](#)", earlier in this chapter. For details about returning whether a specified file is present on the IIS side of the firewall when using the JADE HTML thin client interface via the **jadehttp** library file, see "[Image Files Created by the JADE Application](#)", earlier in this chapter.

Sample [application-name] Section

The following are examples of an **[application-name]** section in the **jadehttp.ini** file for application types specified by the **ApplicationType** parameter.

```
[Company]
ApplicationType = WebEnabledForms
TcpConnection  = Host1a
TcpPort        = 20000
```

```
ConnectionGroup = CompanyForms
MinInUse        = 1
MaxInUse        = 5
CloseDelay      = 600

[RestCo]
ApplicationType = RestServices
TcpConnection   = Host1a
TcpPort         = 27000
MinInUse        = 5
MaxInUse        = 20
CloseDelay      = 600

[WebCompany]
ApplicationType = WebServices
TcpConnection   = Host1a
TcpPort         = 21000
MinInUse        = 5
MaxInUse        = 15
CloseDelay      = 600
TcpConnection2  = Host2a
TcpPort2        = 21001
MinInUse2       = 5
MaxInUse2       = 15
CloseDelay2     = 600

[HtmlCompany]
ApplicationType = HtmlDocuments
TcpConnection   = Host1a
TcpPort         = 22000
MinInUse        = 2
MaxInUse        = 10
CloseDelay      = 600
TcpConnection2  = Host2a
TcpPort2        = 22001
MinInUse2       = 2
MaxInUse2       = 10
CloseDelay2     = 600
```

[Jadehttp Files] Section

The [Jadehttp Files] section of the **jadehttp.ini** file contains parameters that control firewall security and the location of files uploaded from a Web-enabled application.

Caution To prevent malicious use of files uploaded to Web-enabled applications, the files are removed as soon as the event that resulted in their upload has completed. You should therefore process the file immediately or move it into a directory that is not available from the Web if you require that file for future processing.

The **jadehttp** library derives a path for the **jadehttp.ini**, **jadehttp.log**, and transfer files, ensuring that they are completely secure. The directories are derived from the **jadehttp** library directory for these files, as follows.

1. **JadeHttp** attempts to create the required directories if they do not exist if security permits this. These directories, based on the example **c:\jade\bin\jadehttp.dll** file, are listed in the following table.

Directory	Description	Example
<code>dll-path_dll-name\ini\</code>	For the initialization file and the default error <i>dll-name.htm</i> file	<code>c:\jade\bin_jadehttp\ini\jadehttp.ini</code>
<code>dll-path_dll-name\logs\</code>	For all <i>dll-name</i> logs	<code>c:\jade\bin_jadehttp\logs\jadehttp.log</code>
<code>dll-path_dll-name\transfer\</code>	For the location of any temporary files created during file transfer	<code>c:\jade\bin_jadehttp\transfer\...</code>

2. If the initialization file option to specify the log path is set, the logs directory is not created or used.
3. If the initialization file option to specify the transfer path is set, the transfer directory is not created or used.
4. As the dynamic link library can be renamed, its name is included. The library path therefore does not need to contain any other files, and users cannot access any of the files listed in the previous table.

For details about implementing a TCP/IP connection from the IIS to JADE applications, see "[Connecting to JADE Applications from Internet Information Server \(IIS\)](#)" and "[Configuring JadeHttp for Remote Connections](#)", earlier in this chapter.

The [[Jadehttp Files](#)] section can contain the following parameters.

FileTransferDirectory

Value Type String (*disk-path*)

Default Not specified

Purpose

The **FileTransferDirectory** parameter specifies the directory to which files are uploaded during Web sessions from JADE applications that accept file input in text boxes on Web pages (by using the **webInputType** property of a **TextBox** control with the **Web_InputType_File** setting to upload a file from a Web session).

Note This parameter applies only when the **Firewall** parameter in the [[Jadehttp Files](#)] section of the **jadehttp.ini** file is set to **false** or it is set to **true** and the **FileTransferDirectory** parameter is set to **default** or to a valid directory. (For details, see "[Configuring JadeHttp for Remote Connections](#)", earlier in this section.)

This parameter controls the directory in which any files transferred by using the HTML **InputType=file** option are placed. (The file transfer directory must be a valid directory that is relative to the virtual directory, or IIS server.)

If you define a value for the **FileTransferDirectory** parameter, the transfer directory in the same directory as the **jadehttp** library is neither created nor used. The file transfer directory path cannot be greater than 260 characters. For more details, including the format of the **text** property value of the **TextBox** control, see "[Controlling the Location of Files Uploaded via a Web Application](#)", earlier in this chapter.

Firewall

Value Type Boolean

Default False

Purpose

The **Firewall** parameter controls whether firewall separation is used when transferring files to JADE from Web browsers. When this parameter is set to the default value of **false**, files are written to the transfer directory directly by the **JadeHttp** library.

The firewall must be enabled at both ends of the connection (that is, if you are uploading images from another machine for a JADE Web-enabled form over a TCP/IP connection, the **Firewall** parameter in the [Jadehttp Files] section of the JadeHttp initialization file and the **Firewall** parameter in the [WebOptions] section of the JADE initialization file must both be set to **true**).

For details about the handling of data from the user's browser through to JADE, see "[Configuring JadeHttp for Remote Connections](#)", earlier in this section.

Set this parameter to **true** if you want files transferred to the JADE application over the TCP/IP connection. Each file transferred from a Web browser is sent to the JADE application as a separate message. Your JADE application must distinguish this message from a normal Web browser request and store the transferred file. For more details, including the format of messages sent through the firewall, see "[Firewall for the JADE Internet Environment](#)", earlier in this chapter.

Sample [Jadehttp Files] Section

The following is an example of a [Jadehttp Files] section in the `jadehttp.ini` file.

```
[Jadehttp Files]
FileTransferDirectory = c:\jade\bin_jadehttp\transfer
Firewall              = true
```

[Jadehttp Logging] Section

The [Jadehttp Logging] section of the `jadehttp.ini` file controls logging by the `jadehttp` library file. For details about the messages that are logged when tracing is set, see "[Message Logging](#)", in the *JADE Web Application Guide*.

The [Jadehttp Logging] section can contain the following parameters.

Trace

Value Type Boolean

Default False

Purpose

The **Trace** parameter controls `jadehttp` library file logging of message meta data. When this parameter is set to the default value of **false**, logging is suppressed completely.

When the value of this parameter is set to **true**, logged messages acknowledge only that a message has been received or sent, because it is not possible to distinguish what is sensitive data and what is not. Setting this parameter to **true** does *not* include any of the text sent or received from the client, as this text could contain personal information, passwords, credit card details, and so on.

Note You cannot use this parameter to inspect and debug data passing through the `jadehttp` library.

TraceFile

Value Type String (*file-path*)

Default Default

Purpose

The **TraceFile** parameter specifies an optional path and a file name that overrides the default `jadehttp.log` file name so that log files can be placed in other directories.

If you define a value for the **TraceFile** parameter, the log file in the same directory as the **jadehttp** library is neither created nor used. The file transfer directory path cannot be greater than 260 characters.

Sample [Jadehttp Logging] Section

The following is an example of a [\[Jadehttp Logging\]](#) section in the **jadehttp.ini** file.

```
[Jadehttp Logging]
Trace      = true
TraceFile = c:\jade\bin_jadehttp\logs\jadehttp.log
```

Configuring Apache for Remote Connections

TCP/IP connections only are used for connections to JADE applications running from the Apache HTTP Server. This section covers the following topics.

- [Apache Configuration Directives](#)
- [Apache Configuration Examples](#)
- [Apache Considerations](#)

For details about installing the **mod_jadehttp** library module supplied by JADE for the Apache HTTP Server and the MPMs that it implements, see "[Connecting to JADE Applications from an Apache HTTP Server](#)", earlier in this chapter.

Apache Configuration Directives

The configuration directives in this section are available to configure the JADE **mod_jadehttp** module. It uses the standard Apache configuration syntax, rather than implementing configuration via an initialization file.

Set the value of the **JadeHttp_Trace** directive to **true** to ensure the security of your data.

The concept and intent of these directives is the same as the **jadehttp.ini** file parameters, but the syntax differs. For details about the **jadehttp.ini** file parameters, see "[Configuring JadeHttp for Remote Connections](#)", earlier in this chapter.

Most of the directives specific to **mod_jadehttp** have the same meaning as their IIS counterparts (described in "[Controlling the Location of Files Uploaded via a Web Application](#)" under "[Configuring JadeHttp for Remote Connections](#)", earlier in this chapter). The JADE **mod_jadehttp** module configuration directives are as follows.

- [SetHandler](#)
- [ApplicationType](#)
- [Application](#)
- [FaultDocument](#)
- [FileTransferDirectory](#)
- [Firewall](#)
- [JadeHttp_Trace](#)
- [JadeServer](#)
- [JadeTimeout](#)
- [LocalInterface](#)

- [MaxMessageSize](#)
- [MinMessageSize](#)
- [PhysicalDirectory](#)
- [PurgeDirectoryFrequency](#)
- [PurgeDirectoryRule](#)
- [PurgeFileAge](#)
- [TcpConnection\[n\]](#)
- [VirtualDirectory](#)

For details, see the following subsections.

To specify that TCP/IP connections are used to connect to JADE applications from Apache, you must define a **<Location>** directive within `jadehttp.conf` for each application, with an **ApplicationType** directive and unique multiple **TcpConnection[n]** directives between each **Application** directive.

The following `mod_jadehttp` directives apply between the core Apache **<Location>** and **</Location>** directives. Apache processes the **<Location>** directives in the order in which they are found in the configuration file, following any **<Files>** and **<Directory>** sections and after `.htaccess` files have been read and processed.

```
<Location /jade>
    SetHandler jadehttp-handler
    ApplicationType WebServices
    Application WebApplication
    TcpConnection PC1 21000 5 15 300
</Location>
```

This allows `mod_jadehttp` directives to be placed in higher locations and their values to become the defaults for lower locations unless you explicitly override them.

In the following example, the handler and **FaultDocument** directive specified in **<Location /jade>** also apply to **<Location /jade/subloc>**.

```
<Location /jade>
    SetHandler jadehttp-handler
    FaultDocument PostTooLarge "http://server/ohdarn.html"
</Location>
<Location /jade/subloc>
    ApplicationType WebEnabledForms
    Application WebApplication
    TcpConnection PC1 21000 5 10 200
</Location>
```

SetHandler

The standard **SetHandler** Apache directive, whose characteristics are listed in the following table, selects the `mod_jadehttp` module to handle this location.

Characteristic	Value
Action	Forces all matching files to be processed by a handler
Syntax	SetHandler <i>handler-name</i>

Characteristic	Value
Context	server config, virtual host, directory, .htaccess
Module	Core
Examples	SetHandler jadehttp-info and SetHandler jadehttp-handler

The **jadehttp-handler**, which is the primary handler inside the **mod_jadehttp** module, formats and passes data to JADE and returns the results to the Web browser. The **jadehttp-info** handler reports internal information about the configuration and current status of the **mod_jadehttp** module back to the Web browser. This handler is similar to the standard Apache **mod_info** module that provides a comprehensive overview of the server configuration. Access to locations that use this handler should be restricted to trusted sites.

ApplicationType

The **ApplicationType** directive specifies the type of application that will be supported and how the interfaces to JADE function.

Note You must define this directive *before* the **TcpConnection[n]** directive within each **Application** directive.

The application type characteristics are listed in the following table.

Characteristic	Value
Action	Specifies the JADE application type
Syntax	ApplicationType <i>application-type</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Example	ApplicationType RestServices

The valid application type values are listed in the following table.

Value	Description
RestServices	Representational State Transfer (REST) lightweight Web service that embraces HyperText Transfer Protocol (HTTP) through Extensible Markup Language (XML) or JavaScript Object Notation (JSON) messages instead of SOAP.
WebEnabledForms	<p>Web-enabled forms. This application type results in all requests from a user being directed to the same JADE application copy during the user's session. JadeHttp no longer inserts the tags into the HTML output; the JADE software now performs this function.</p> <p>The JADE side uses the multi-worker TCP facility to perform routing and queuing.</p> <p>Note For the WebEnabledForms application type, you must specify the MinInUse, MaxInUse, CloseDelay, and ConnectionGroup values for the TcpConnection[n] directive.</p>
WebServices	<p>Web service operation, where user requests are sent to any available connection.</p> <p>The JADE side uses the multi-worker TCP facility to perform routing and queuing.</p>

Value	Description
HtmlDocuments	HTML documents operation where user requests are sent to any available connection. The JADE side uses the multi-worker TCP facility to perform routing and queuing.

Application

The **Application** directive, whose characteristics are listed in the following table, specifies the name of the Web-enabled JADE application.

Characteristic	Value
Action	Specifies the JADE application to use
Syntax	Application <i>application-name</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Example	Application ErewhonShop

This directive is similar to the functionality of the [*application-name*] section of the **jadehttp** library module for IIS, described earlier in this chapter.

FaultDocument

The **FaultDocument** directive, whose characteristics are listed in the following table, specifies what the **mod_jadehttp** module does when it encounters an error.

Characteristic	Value
Action	Specifies the URL or path name for redirection when an error occurs
Syntax	FaultDocument <i>cause redirect-url</i>
Context	Location
Handler	jadehttp-handler, jadehttp-info
Module	mod_jadehttp
Example 1	FaultDocument TcpConnectFailed http://secondary.example.com:80/page.html
Example 2	FaultDocument PostTooLarge bigpost.html

You can specify the *cause* value in numeric or text form. Valid values for the *cause* are listed in the following table.

Numeric Name	Text Name
600	TcpConnectFailed
601	PostTooLarge
602	ServiceFailed
603	DataReadFailed

You must specify a valid URL or path name for the *redirect-url* value, which can be on the local Web server or on a remote Web server. If you do not specify a *redirect-url* value and an error occurs, an error page is raised internally in the **mod_jadehttp** module.

FileTransferDirectory

The **FileTransferDirectory** directive, whose characteristics are listed in the following table, specifies the name of a local directory to use when files are uploaded from the Web browser to the JADE application.

Characteristic	Value
Action	Specifies the directory to use when files are uploaded from the Web browser
Syntax	FileTransferDirectory <i>local-directory-name</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Example	FileTransferDirectory /var/tmp/appname

The **FileTransferDirectory** directive is similar to the **FileTransferDirectory** parameter in the [Jadehttp Files] section of the **jadehttp.ini** file for IIS servers, described earlier in this chapter.

As the **mod_jadehttp** module must put the transfer files somewhere before transferring them to JADE, this directive specifies the directory to which the file or files are written.

Firewall

The **Firewall** directive, whose characteristics are listed in the following table, specifies whether there is a firewall between the **mod_jadehttp** module and the JADE application.

Characteristic	Value
Action	Indicates if there is a firewall between mod_jadehttp and JADE
Syntax	Firewall on off
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Example	Firewall on

The **Firewall** directive is similar to the **Firewall** parameter in the [Jadehttp Files] section of the **jadehttp.ini** file for IIS servers, described earlier in this chapter. If a firewall is present, file transfers between JADE and the Web server must be done by using the **mod_jadehttp** module.

The firewall must be enabled at both ends of the connection (that is, if you are uploading images from another machine for a JADE Web-enabled form over a TCP/IP connection, the **Firewall** configuration directive in the JADE **mod_jadehttp** module must be set to **on** and the **Firewall** parameter in the [WebOptions] section of the JADE initialization file must be set to **true**).

When transferred, the files will be placed in the directory specified in the **PhysicalDirectory** directive.

JadeHttp_Trace

The **JadeHttp_Trace** directive, whose characteristics are listed in the following table, controls where any **mod_jadehttp** tracing is written.

Characteristic	Value
Action	Specifies the log file to which JADE trace messages are sent
Syntax	<code>JadeHttp_Trace bit-mask [file-name [size[K M]]]</code> <code>JadeHttp_Trace bit-mask " rotatelog-program rotatelog-arguments"</code>
Context	Server config, virtual host, Location
Module	<code>mod_jadehttp</code>
Examples	<code>JadeHttp_Trace 0x000000ff logs/jade%Y%m%d%H%M%S.log 10M</code> <code>JadeHttp_Trace 0x000000ff " usr/sbin/rotatelog2 -l /var/logs/apache2/jadehttp_%Y%m%d%H%M.log 10M"</code>

The **JadeHttp_Trace** directive is similar to the **Trace** and **TraceFile** parameters in the [**Jadehttp Logging**] section of the **jadehttp.ini** file, documented earlier in this chapter.

If this parameter is not specified, logging is suppressed completely. Specifying this parameter ensures the security of your data. When the value of this parameter is specified, logged messages acknowledge only that a message has been received or sent, because it is not possible to distinguish what is sensitive data and what is not. When this parameter is specified, messages logged to the **jadehttp.log** file do not include any of the text sent or received from the client, as this text could contain personal information, passwords, credit card details, and so on.

Note You cannot use this parameter to inspect and debug data passing through the **jadehttp** library.

If the *file-name* is relative, it is created relative to the **ServerRoot** location. If you do not specify the *file-name*, it defaults to **"logs/jadehttp%Y%m%d%H%M%S.log"**.

If you do not specify the *size*, it defaults to **5M** bytes. To disable **mod_jadehttp** from attempting to rotate log files, specify a *size* of zero (**0**). The *size* value can have a multiplier appended to it. The **K** multiplier multiplies by **1,024**, the **M** multiplier multiplies by **1,048,576** bytes, and all other values are treated as bytes.

If the *file-name* is in a directory that an Apache child **httpd** process does not have permission to access, the rotation of logs is disabled in **mod_jadehttp**. The file name can include **%** modifiers, which specify values from the current local time (based on the Apache **rotatelog2** program, whose documentation is available at <http://httpd.apache.org/docs/2.4/programs/rotatelog.html>, for example), permitted values are **AaBbcdHijMmSUWwXxYyZ%.2.4.10**

If no **%** modifiers are present, **"%Y%m%d%H%M%S"** is appended at the end of the file name (before the file extension, if it exists). This adds year, month, day, hour, minute, and second values to the file name.

A new log file is created if the file name changes (due to the changing time and selected modifier values) and if the file exceeds the specified size.

Note Multiple log files could be actively written to concurrently, because of the way that the Apache pre-fork MPM works.

Alternatively, you can use an external program to get log files rotated; for example, the one that is normally provided with the **rotatelog2** Apache distribution. This works well when log files are placed in a directory where the Apache child process does not have permission to create files.

The use of an external program behaves the same way as the Apache piped logs feature, which is described in the Apache documentation. It involves specifying the rotate program and arguments inside double quote characters (""), with the first character of the string being the pipe (|) character.

Note The name of the **rotatelog**s program can differ, depending on your Apache distribution and operating system.

The bit set values for the *bit-mask* value are listed in the following table.

Bit Set	Description
0x00000001	When a redirect occurs
0x00000002	When a special command is issued
0x00000004	When file purges occur
0x00000008	When mod_jadehttp sends connection information to JADE

JadeServer

The **JadeServer** directive, whose characteristics are listed in the following table, is reserved for future implementation.

Characteristic	Value
Action	Specifies the JADE server configuration
Syntax	<i>JadeServer jade-version byte-order character-size</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Default	JadeServer 7.1 <i>localEndian</i> oneByte
Example	JadeServer 7 Intel utf-16

This directive allows a single **mod_jadehttp** module to connect to JADE, regardless of the combination of Web server architecture and JADE server architecture, allowing **mod_jadehttp** to adapt to the installed release of the JADE server.

The *jade-version* value allows for the protocol to between JADE and the **mod_jadehttp** module to be changed. The version number can be in the range 1 through 4, with each number separated with numbers inclusive separated with the dot operator (.) notation; for example, **7.1.05.007**.

The *byte-order* value allows for binary numbers and wide characters to be converted to the native byte ordering of the JADE server, which may be different from the byte ordering of the Web server.

In the default example in the previous table, the *localEndian* value defaults to **littleEndian** when the **mod_jadehttp** module is running on Intel-based hosts and **bigEndian** when on PowerPC-based hosts. The entered value is not case-sensitive.

The primary names and synonyms for the *byte-order* value are listed in the following table.

Primary Name	Synonym
littleEndian	Intel
bigEndian	PowerPC

The *character-size* value indicates the size of a JADE character, which is ANSI or Unicode, depending on your JADE installation. If the character size is Unicode where the JADE server is running, the physical size of a JADE character can be one of 1, 2, or 4 bytes in size. This allows **mod_jadehttp** to send JADE characters of the correct size and type to the JADE server.

The primary names and synonyms for the entered value, which is not case-sensitive, are listed in the following table.

Primary Name	Synonym
oneByte	ANSI
twoByte	Unicode, Utf16, or Utf-16
fourByte	Utf32 or Utf-32

JadeTimeout

The **JadeTimeout** directive, whose characteristics are listed in the following table, specifies the maximum number of seconds that **mod_jadehttp** waits for a reply from a JADE system before sending a failure message to the requesting Web browser.

Characteristic	Value
Action	Specifies the maximum number of seconds to wait for a reply from JADE
Syntax	JadeTimeout <i>number-of-seconds</i> (the default value is 45 seconds)
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Default	JadeTimeout 300 (that is, 5 minutes)
Example	JadeTimeout 30

A default value of zero (**0**) indicates that there is not timeout. The maximum timeout value is **1800** (that is, 30 minutes).

Hints

This directive enables you to test the effects of unexpectedly long request processing without having to wait the default five minutes for each test.

When Web-enabled applications are all busy, you can control the time that a Web browser window shows no action before returning the *Service unavailable* response.

LocalInterface

The **LocalInterface** directive, whose characteristics are listed in the following table, specifies the local network interface and optionally the port number to use when connecting from the **mod_jadehttp** module to the JADE Web-enabled application.

Characteristic	Value
Action	Specifies the local network interface and optionally the port number
Syntax	LocalInterface <i>local-network-interface-handler-name</i>

Characteristic	Value
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Default	LocalInterface 0.0.0.0
Example	LocalInterface 10.1.1.1

If your Web server host has multiple network interface cards, you can specify which one **mod_jadehttp** uses when initiating connections to the Web-enabled JADE application.

The default value of **0.0.0.0** allows the operating system to choose the network interface card.

You would normally require this directive only when there are specific network security or routing issues to be addressed.

Caution Although you can also specify the local outgoing port number, you should take great care when doing so and only when you have a specific requirement. Specifying a **LocalInterface** port number limits you to a maximum of one TCP/IP connection to JADE for each Apache **<Location>** directive. In addition, if the Web server terminates abnormally and the port is not properly closed, it may take several minutes before this port becomes available again for use.

MaxMessageSize

The **MaxMessageSize** directive, whose characteristics are listed in the following table, specifies the largest size of a **POST** URL before an error is raised.

Characteristic	Value
Action	Specifies the maximum size of a POST string
Syntax	MaxMessageSize <i>size</i> [<i>M K</i>]
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Default	MaxMessageSize 1M
Example	MaxMessageSize 50K

You can append a multiplier to the *size* value. The **M** multiplier multiplies by **1,048,756**, the **K** multiplier multiplies by **1,024**, and all other values are treated as bytes.

The minimum value is zero (**0**) and the maximum value is **128M**.

MinMessageSize

The **MinMessageSize** directive, whose characteristics are listed in the following table, specifies the minimum size allowed for a Web message received from JADE using the **WebSession** class **reply** method to send HTML string Web requests back to the client node.

Characteristic	Value
Action	Specifies the minimum number of bytes allowed for a Web message from JADE
Syntax	MinMessageSize <i>message-size-in-bytes</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Default	MinMessageSize 10
Example	MinMessageSize 100

The minimum value is 1 byte and the maximum value is **1024** bytes. This value is read once, when the Apache Web server starts.

PhysicalDirectory

The **PhysicalDirectory** directive specifies the name of a local directory to use when files are transferred from JADE to the Web server by using the **JadeWebServiceProvider** or **WebSession** class **createVirtualDirectoryFile** method without specifying a directory in the **fileName** parameter. This directory is also used as the location for transferring files when the **Firewall** directive is set to on. In this situation, it behaves in a similar way to the **FileTransferDirectory** parameter in the [Jadehttp Files] section of the jadehttp.ini file for IIS servers, described earlier in this chapter.

The characteristics of the **PhysicalDirectory** directive are listed in the following table.

Characteristic	Value
Action	Specifies the directory to use as a physical directory
Syntax	PhysicalDirectory <i>local-directory</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Example	PhysicalDirectory /var/tmp/appname/

Note Apache directives require separators to be defined using a forward slash (/) character.

The following is an example of the use of the **PhysicalDirectory** directive.

```
<Directory /var/spool/www/jade/images/>
    order allow,deny
    allow from all
</Directory>

Alias /jade/images/ /var/spool/www/jade/images/
```

```
<location /jade/webform>
  SetHandler jadehttp_handler

  PhysicalDirectory /var/spool/www/jade/images/

</location>
```

In this example, the physical directory on disk `/var/spool/www/jade/images/` needs to be the same in the three places. The actual value can change on a site-specific basis.

PurgeDirectoryFrequency

The **PurgeDirectoryFrequency** directive, whose characteristics are listed in the following table, specifies how often the physical directory is checked to see if files require purging.

Characteristic	Value
Action	Specifies the frequency at which the physical directory is purged
Syntax	<code>PurgeDirectoryFrequency <i>time-unit</i>[H M]</code>
Context	Location
Handler	<code>jadehttp-handler</code>
Module	<code>mod_jadehttp</code>
Default	<code>PurgeDirectoryFrequency 1H</code>
Example	<code>PurgeDirectoryFrequency 5H</code>

You can append a multiplier to the *time-unit* value. The **H** multiplier multiplies by **3,600**, the **M** multiplier multiplies by **60**, and all other *time-unit* values are treated as seconds.

Specify zero (**0**) for the *time-unit* value to turn off the purging of the physical directory.

The minimum that you can specify for the *time-unit* value is **5** minutes and the maximum is **24H** (hours).

Values outside this range are forced to their respective limits.

PurgeDirectoryRule

The **PurgeDirectoryRule** directive, whose characteristics are listed in the following table, specifies when files in the virtual directory that are not read-only are purged.

Characteristic	Value
Action	Specifies when non-read-only files in the virtual directory are purged
Syntax	<code>PurgeDirectoryRule Default AllWritable</code>
Context	Location
Handler	<code>jadehttp-handler</code>
Module	<code>mod_jadehttp</code>
Default	<code>PurgeFileAge Default</code>
Example	<code>PurgeFileAge AllWritable</code>

The default value of **Default** for this directive removes any standard files of type **.jpg**, **.png**, or **.gif** that are more than 12 hours old.

Specify a value of **AllWritable** if you want to purge all files in the virtual directory that are not read-only.

PurgeFileAge

The **PurgeFileAge** directive, whose characteristics are listed in the following table, specifies the length of time since a file was last modified before it is purged from the physical directory.

Characteristic	Value
Action	Specifies the minimum modified age before the files are purged
Syntax	PurgeFileAge <i>time-unit</i> [D H M]
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Default	PurgeFileAge 12H
Example	PurgeFileAge 1D

You can append a multiplier to the *time-unit* value. The **D** multiplier multiplies by 86,400, the **H** multiplier multiplies by **3,600**, the **M** multiplier multiplies by **60**, and all other *time-unit* values are treated as seconds. Specify zero (**0**) for the *time-unit* value to turn off the purging of the physical directory.

The minimum that you can specify for the *time-unit* value is **30** seconds and the maximum is **35D** (days). Values outside this range are forced to their respective limits.

See also the [JadeWebServiceProvider](#) or [WebSession](#) class `deleteVirtualDirectoryFile` method.

TcpConnection[n]

The **TcpConnection[n]** directive can have one of two types of syntax, depending on the value of the [ApplicationType](#) directive. The optional **[n]** value can be a unique number in the range **1** through **9**. If you do not specify the optional *n* group suffix, JADE treats the value as **1**.

You can specify the *host-name* value as a host name or as an IP address. If you specify a host name, it must resolve to a single IP address. If you append the optional *n* value to the **TcpConnection[n]** directive, it indicates the group to which the specified host name port number range is assigned.

If the value of the [ApplicationType](#) directive is **RestServices**, **WebEnabledForms**, **WebServices**, or **HtmlDocuments**, the characteristics listed in the following table specify the TCP/IP connection details between the `mod_jadehttp` module and the JADE Web application.

Characteristic	Value
Action	Specifies the TCP/IP connection to the JADE application
Syntax	TcpConnection[n] <i>host-name</i> <i>port</i> [MinInUse [MaxInUse [CloseDelay [ConnectionGroup]]]]
	Note For the WebEnabledForms application type, you must specify the MinInUse , MaxInUse , CloseDelay , and ConnectionGroup values.
Context	Location

Characteristic	Value
Handler	jadehttp-handler
Module	mod_jadehttp
Example 1	TcpConnection server1 6008
Example 2	TcpConnection2 10.1.1.19 51030 3 15 300
Example 3	TcpConnection3 10.1.1.19 51031 1 10 30 Forms

For details about the optional [MinInUse](#), [MaxInUse](#), [CloseDelay](#), and [ConnectionGroup](#) values, see the following subsections.

MinInUse

The optional **MinInUse** value specifies the minimum number of connections that can be opened for the [TcpConnection\[n\]](#) directive when the value of the [ApplicationType](#) directive is set to **RestServices**, **WebServices**, or **HtmlDocuments**.

This value must be specified when the [ApplicationType](#) directive is set to **WebEnabledForms**.

The default minimum number of connections is **1**.

MaxInUse

The optional **MaxInUse** value specifies the maximum number of connections that can be opened for the [TcpConnection\[n\]](#) directive when the value of the [ApplicationType](#) directive is set to **RestServices**, **WebServices**, or **HtmlDocuments**.

This value must be specified when the [ApplicationType](#) directive is set to **WebEnabledForms**.

The default maximum number of connections is the value of [MinInUse](#).

Note The **MaxInUse** value is forced to be equal to or greater than the [MinInUse](#) value.

CloseDelay

When the current number of in-use connections for the [TcpConnection\[n\]](#) directive exceeds the [MinInUse](#) value, you can specify the optional **CloseDelay** value to indicate how many seconds before the extra connections are closed after they become inactive.

This value must be specified when the [ApplicationType](#) directive is set to **WebEnabledForms**.

The close delay defaults to zero (**0**) seconds before inactive connections are closed, indicating that the connection is never closed. The maximum value is **300** seconds.

ConnectionGroup

The optional **ConnectionGroup** value specifies the name of the connection group associated with the [TcpConnection\[n\]](#) directive; that is, the unique name that is used by applications of type **WebEnabledForms** to identify the TCP/IP port to which a user request is to be sent.

Although there is no default connection group, you must specify a unique value when the value of the [ApplicationType](#) directive is set to **WebEnabledForms**.

VirtualDirectory

The **VirtualDirectory** directive, whose characteristics are listed in the following table, is an easier way to specify the same value as the **PhysicalDirectory** directive.

The **VirtualDirectory** directive is mainly of use when the same **jadehttp.conf** file is designed to run on multiple hosts.

Characteristic	Value
Action	Specifies the TCP/IP connection to the JADE application
Syntax	VirtualDirectory <i>directory-name</i>
Context	Location
Handler	jadehttp-handler
Module	mod_jadehttp
Example	VirtualDirectory /var/web/myWebApp/files

The following is an example of the use of the **VirtualDirectory** directive.

```
<IfModule mpm_winnt.c>
  <Directory "c:/temp/">
    ...
  </Directory>
  Alias /jade/images/ "c:/temp/"
</IfModule>

<IfModule !mpm_winnt.c>
  <Directory "/tmp/">
    ...
  </Directory>
  Alias /jade/images/ "/tmp/"
</IfModule>
<location /jade/webform>
  SetHandler jadehttp_handler

  VirtualDirectory /jade/images/

</location>
```

In this example, depending on where this **jadehttp.conf** file is used, the physical directory to which transferred files are written is different. The **VirtualDirectory** directive uses the URL location of **/jade/images/** to determine the actual directory name to use. For details about retaining files passed to **mod_jadehttp**, see "[Firewall for the JADE Internet Environment](#)", earlier in this chapter.

Apache Configuration Examples

In the configuration examples in this section, the following has assumed to have been added to the **httpd.conf** file, which is the default main configuration file for Apache.

The primary Apache configuration file is normally called **httpd.conf**. You can place **mod_jadehttp** directives in this file or in a separate file.

The recommended method is to create a separate **jadehttp.conf** file that contains the required **mod_jadehttp** directives, and include this file in the primary **http.conf** file as follows.

```
LoadModule jadehttp_module modules/mod_jadehttp.so
Include conf/jadehttp.conf
```

Each of the examples in the following subsections has a different **jadehttp.conf** file.

Minimal Configuration Example

The following is a minimal example of the **jadehttp.conf** file that enables you to connect to the JADE example **Erewhon** system and access the Web shop.

```
<IfModule mod_jadehttp.c>
<Directory "/pictures">
    Order deny,allow
    Allow from All
</Directory>

Alias /jadeImages/ "/pictures"

    <Location /jade-info>
        SetHandler jadehttp-info
        order deny,allow
        allow from localhost
    </Location>
    <Location /Erewhon>
        SetHandler jadehttp-handler
        ApplicationType WebEnabledForms
        Application WebShop
        TcpConnection jadeserver 6007 3 15 300 Forms
        VirtualDirectory /jadeImages/
    </Location>
</IfModule>
```

From your Web browser, use the **http://webserver/Erewhon** URL to connect to the example **Erewhon** system.

To find out status information about what is happening inside the **mod_jadehttp** module, use the **http://localhost/jade-info** URL on the workstation running the Apache Web server.

Extended Configuration Example

Add the following to the **jadehttp.conf** file, referred to in the **httpd.conf** file under "[Apache Configuration Examples](#)", earlier in this chapter (or you can include it in the **httpd.conf** file itself).

```
<IfModule mod_jadehttp.c>

    <Location /jade>
        SetHandler jadehttp-handler
        FaultDocument TcpConnectFailed "/messages/CanNotConnect.html"
    </Location>

    <Location /jade/info>
        SetHandler jadehttp-info
    </Location>

    <Location /jade/Erewhon>
        ApplicationType RestServices
```

```

        Application RestTestApp
        TcpConnection cnwjdc1a 6007 1 10
    </Location>

    <Location /jade/Erewhon>
        ApplicationType WebServices
        Application Erewhon
        TcpConnection cnwjdc1a 6007 1 10
    </Location>

    <Location /jade/erewhon/user>
        ApplicationType WebEnabledForms
        Application UserApp
        TcpConnection cnwjdc1a 6007 3 10 30 Group1
    </Location>

    <Location /jade/erewhon/admin>
        ApplicationType WebServices
        Application AdminApp
        TcpConnection cnwjdc1a 6018
    </Location>

</IfModule>

```

Extended Configuration Example with Additional Apache Directives

Add the following to the `jadehttp.conf` file, referred to in the `httpd.conf` file under "[Apache Configuration Examples](#)", earlier in this chapter (or you can include it in the `httpd.conf` file itself).

```

<IfModule mod_jadehttp.c>

    <Location /jade-info>
        JadeHttp_Trace 0xffff Logs/jadehttp.log 5M
        SetHandler jadehttp-handler
        FaultDocument TcpConnectFailed "/messages/CanNotConnect.html"
        ErrorDocument 503 "http://localhost:8080/messages/Custom503.html"
    </Location>

    <Location /jade/info>
        SetHandler jadehttp-info
        Order deny,allow
        Deny from all
        Allow from 127.0.0.0/8 10.1.1.100
    </Location>

    <Location /jade/BankOfJade>
        JadeHttp_Trace 0xff
        ApplicationType HtmlDocuments
        Application BankApp
        ConnectionGroup FinanceDepartment
        TcpConnection cnwjdc1a 6007
        Order deny,allow
        Deny from all
        Allow from 192.168.0.0/16
    </Location>

```

```

<Location>
  ApplicationType WebEnabledForms
  Application Company
  ConnectionGroup Customers
  TcpConnection Host1a 2000 1 5 300 CompanyForms
  Order allow,deny
  Allow from all
</Location>

<Location /jade/erewhon/user>
  ApplicationType WebServices
  Application WebCompany
  TcpConnection Host1a 21000 5 15 300
  TcpConnection2 Host2a 21001 5 15 300
  Order deny,allow
  Deny from all
  Allow from 143.96.0.0/16
</Location>

<Location /jade/erewhon/user>
  ApplicationType RestServices
  Application RestTestApp
  TcpConnection Host1a 26000 2 10 300
  TcpConnection2 Host2a 26001 2 10 300
  Order allow,deny
  Allow from all
</Location>

<Location /jade/erewhon/user>
  ApplicationType HtmlDocuments
  Application HtmlCompany
  TcpConnection Host1a 22000 2 10 300
  TcpConnection2 Host2a 22001 2 10 300
  Order allow,deny
  Allow from all
</Location>

<Location /jade/erewhon/admin>
  ApplicationType WebServices
  Application WebCompany
  TcpConnection Host1a 21000 5 15 300
  TcpConnection2 Host2a 21001 5 15 300
  Order deny,allow
  Deny from all
  Allow from 127.0.0.0/8
</Location>

</IfModule>

```

Apache Considerations

When using the Apache HTTP Server to connect to your JADE applications from the Internet, consider the following.

- The JADE Web design considerations documented under "[Connecting to JADE Applications from an Apache HTTP Server](#)", earlier in this chapter.
- Only [JadeInternetTCPConnection](#) class TCP/IP communications are supported. This applies to all

versions of `mod_jadehttp`, regardless of the operating system.

- The security implications for `mod_jadehttp` are those of the IIS `jadehttp.dll`. Access to JADE data from the Web server can be controlled by Apache security directives.
- Apache and the HTTP generally use UTF-8 as the encoding scheme for Unicode data on the Web. As `mod_jadehttp` does not allow for this and passes the data directly to JADE, only ANSI data can be read or written to the `JadeInternetTCPIPConnection` object.
- As the `JadeServer` configuration directive that indicates details about the JADE application to which `mod_jadehttp` is connected is not yet implemented, it is assumed that the value of this directive is as follows.

```
JadeServer 7.1 littleEndian Ansi
```

Tuning Your Systems

The JADE object manager uses a default hash value of:

- 2053, when storing and locating persistent and transient locks. You can vary these hash values (for example, for systems that are likely to have a large number of concurrent persistent or transient locks) by using the `PersistentLockHashSize` or `TransientLockHashSize` parameter in the `[JadeClient]` and `[JadeServer]` sections of the JADE initialization file.
- 1019, for notifications. You can vary this hash value (for example, for systems that have a large number of notifications registered) by using the `NotificationHashSize` parameter in the `[JadeClient]` and `[JadeServer]` sections of the JADE initialization file.

Specifying Parameters in the JADE Command Line

The JADE command line (or program target), used when running a JADE application from outside of the development environment, contains parameters that enable you to specify your JADE configuration. Each element of the command line has an identifying prefix, followed by an equals sign (=) and a specified value.

Command line elements can be delimited by a space, a tab, or a comma. Parameters containing these delimiters must be enclosed in single quotes (") or double quote (") characters.

Notes You can define parameters in the `[JadeCommandLine]` section of the JADE initialization file that you would normally specify on the command line and you can define two-level initialization file section names so that multiple programs on the same host can share a JADE initialization file. For details, see "[Two-Level Section Names](#)" and "[Sharing JADE Initialization Files](#)", in the *JADE Initialization File Reference*. See also "[Placing Initialization File Parameters on the Command Line](#)", in the following subsection.

As the command line structure of the batch JADE Database utility program (`jdbutilb`) differs from that of other JADE applications, the specification of a command line **name** parameter that matches an initialization file section unique identifier does not apply.

Unless your JADE initialization file is located in the `bin` directory, specify the `ini` parameter on the shortcut command line rather than in the `[JadeCommandLine]` section so that the executable knows immediately the location of the JADE initialization file that contains all information required by the program.

You can use the `server` parameter in a command line to specify the server Universal Resource Identifier (URI) target database and the client-server transport, instead of the `server` and `path` parameters in a command line and the `ServerNodeSpecifications` parameter in the `[JadeClient]` section of the JADE initialization file. For details, see "[Format of the Server URI String](#)", earlier in this chapter.

For details about:

- Running JADE in thin client mode, see "[Invoking a JADE Presentation Client](#)" under "[Running the Application Server and Presentation Clients](#)", in Chapter 2 of the *JADE Thin Client Guide*
- Running a JADE client application as a standard (fat) client or a presentation (thin) client from the JADE executable (**jade.exe**) command line, see "[Running a JADE Client Application using jade.exe](#)", in Chapter 1 of the *JADE Runtime Application Guide*
- For information about the parameters that enable you to handle multiple copies of JADE, see "[Handling Multiple Copies of the JADE Program](#)", later in this chapter

The command line parameters are listed in the following table.

Parameter	Specifies ...	Example
app	Application name	app=Jade
path	Full path of your JADE database directory containing your *.dat JADE files	path=c:\jade\system
schema	Schema name (mandatory except when app=Jade)	schema=Faults
ini	JADE initialization file path	ini=c:\jade\system\jade.ini
[server]	Server type	server=SingleUser
[thinClient]	That jade.exe checks only arguments required to run in thin client mode	thinClient=false
[name]	That the program checks for a matching initialization file section name	name=SecureAppServer
[newcopy]	A new copy of jade.exe is to be started	newcopy=false
[host]	Host server node name or IP address	host=cnwchcs38
[port]	Port name or number of the host (server) node	port=6015
[interface]	TCP/IP name or the IP address of the client (local) node	interface=cnwme1c
[localport]	Port name or number of the client (local) node	localport=5017
[appServer]	Remote TCP/IP address or name of the application server	appServer=JadeServer
[appServerPort]	TCP/IP port number of the application server	appServerPort=1500
[StartAppParameters] and [EndAppParameters]	Arguments to enable HugeStringArray string elements to be collected from the command line arguments and passed to the initialization method so that you can run non-GUI standard or thin clients from the jade executable command line	StartAppParameters fileName = "g:\temp\manifest today.txt" report codecoverage=true output=true g:\temp\UnitTest.log EndAppParameters
[endJade]	The end of JADE-specific parameters (applicable only to the non-GUI client jadclient program, and ignored for all other JADE programs)	endJade
[arguments]	Optional user-defined parameters for the jadclient program	MyNonJadeApp.exe

When specifying your JADE command line:

- You must include the application (**app**) parameter.
- You must include the **schema** parameter (except when **app=Jade**).

- For JADE executables, you must include fully qualified name of your JADE initialization file in the **ini** parameter.
- You must include the path (**path**) parameter. The **path** parameter specifies the location of the JADE database. The database path cannot be greater than 260 characters.

When running in multiuser mode, the path is always relative to the viewpoint of the server node; for example, **c:\jade\system** refers to the **c:** drive of the server node and not that of the local client workstation.

You should specify the fully qualified path name.

When you specify a relative path name in the **path** parameter of the command line, the path name is first converted to an absolute path, by using the following rule.

- A relative path name with a single leading slash character is pre-pended by the first two characters of the JADE HOME directory on the server node (that is, **drive-letter:**), which is assumed to be the parent of the **bin** directory. For example, if your installation directory is **Jade\bin** (that is, your JADE HOME directory is **Jade**) and you specify **path=system**, the full directory path is **Jade\system** on the server).

In the following examples, the JADE HOME directory is assumed to be **c:\jade**.

Path Specified in the Command Line	Actual Path
path=/jade71/system	c:/jade71/system
path=system	c:/jade/system

- The **ini** parameter specifies the location of the JADE initialization file. Letters specifying the drive are relative to the viewpoint of the client node. The initialization file defaults to **Jade.ini**, located in your database (system) path.
- The optional **server** parameter specifies **SingleUser** or **MultiUser**.

Note If you do not specify a **server** value, the **Server** parameter in the [Jade] section of the JADE initialization file is used. If this parameter is not specified in the JADE initialization file, the server defaults to **MultiUser**.

- When you specify the name of a port rather than the number in the optional **port** parameter, the port name cannot start with a numeric value.
- Identifying prefixes are case-insensitive.
- Spaces are required only between the end of one parameter and the start of the next.
- Names and paths with embedded spaces should be enclosed in double quote characters ("").
- If you want to specify parameters to your JADE non-GUI client application, specify the **endJade** parameter as the last of the JADE parameters before the first of your own parameters in the **jadclient** command line.

The **jadclient** program treats processing arguments enclosed in double ("") or single (") quotation marks after the **endJade** parameter as single-string entries in the huge string array. The handling of strings in this huge string array is application-specific. For example, **dir= "program files"** is treated as a two-string entry and **"dir= program files"** is treated as a one-string entry. How these entries are handled is determined by your application.

Note All other programs (for example, **jade.exe**, **jadapp.exe**, and **jadload.exe**) do not parse the command line beyond the **endJade** parameter, so any subsequent arguments will be ignored.

- Specify parameters (options) once only, in any order.

If a parameter on the command line is duplicated, the last occurrence found on the command line is used.

- When running JADE thin client applications in multiuser mode, ensure that the TCP/IP port number specified in the **jadapp** (or **jadappb**) command line **appServerPort** parameter is a different port number from that specified for the database server (for example, the **jadrap** JADE Remote Node Access program).

The database server TCP/IP port number is specified in the **ServerNodeSpecifications** parameter remote port value in the **[JadeClient]** section and the **NetworkSpecification** parameter *IP-address* value in the **[JadeServer]** section of the JADE initialization file.

In multiuser mode, you can optionally use:

- The **host** command line parameter, to specify the host server node name or IP address.

This parameter specifies a host name that is resolvable by the Domain Name Server (DNS) or host file, and has a maximum length of **255** characters.

- The **port** command line parameter, to specify the host port name or number.

If you use this parameter to specify the port name, you must update the applicable file in a Windows operating system, as follows.

```
/<winnt>/system32/drivers/etc/services
/ <windows9x>/services
```

Note A port name cannot begin with a numeric value.

- The **interface** command line parameter, to specify the client (local) node name or IP address.

This parameter specifies a host name that is resolvable by the Domain Name Server (DNS) or host file, and has a maximum length of 255 characters.

- The **localport** command line parameter, to specify the client (local) port name or number.

If you use this parameter to specify the local port name, you must update the applicable file in a Windows operating system, as follows.

```
/<winnt>/system32/drivers/etc/services
/ <windows9x>/services
```

Note A local port name cannot begin with a numeric value.

Specify the optional **interface** and **localport** parameters if you want to bind a specific network adapter in a server node that has more than one network adapter installed; for example, to allow an administrator to ensure connections from clients connect on the fastest interface or to allow easier security when used in conjunction with a firewall or router access list. (By default, JADE defaults to the primary network adapter in the node.)

If you do not specify a **host** or a **port** parameter, the **ServerNodeSpecifications** parameter value in the **[JadeClient]** section of the JADE initialization file is used. If neither of these values is specified in the JADE initialization file, they default to **LocalHost** and **6005**, respectively.

The **host**, **port**, **interface**, and **localport** command line parameters, if specified, override (but do not update) the **ServerNodeSpecifications** parameter [*host-name* or *IP-address*], [*remote-port*], [*local-interface-name* or *IP-address*], or [*local-port*] values, respectively, in the **[JadeClient]** section of the JADE initialization file.

If you are running multiple copies of JADE, you can have multiple **jade.exe** shortcuts using the same JADE initialization file (**jade.ini**) by using the optional **name** parameter, instead of having separate files for each copy of JADE that you run. For details about multiple JADE programs on the same host sharing a JADE initialization file, see "[Sharing JADE Initialization Files](#)", in the *JADE Initialization File Reference*.

Placing Initialization File Parameters on the Command Line

You can override any JADE initialization file values by placing them on the command line.

Note For JADE executables, specify the fully qualified name of your JADE initialization file in the command line.

JADE first looks for command line parameters of the form *section-name.parameter-name=value* and if not present, checks the JADE initialization file for the section name and parameter name combination.

Two-level section names are supported in the command line.

Placing JADE initialization file entries on the command line enables:

- JADE developers and system administrators to quickly test alternative configurations, rather than having to create multiple JADE initialization files.
- JADE developers to share one JADE initialization file.

For example, to allow specific application servers to run specified applications only, on the command line, specify the **jadapp** application server executable shortcut command line as follows.

```
R:\Test\jade\bin\jadapp appServerPort=1500 thinClient=true path=r:\test\jade\system
ini=r:\jade\system\test\myjade.ini JadeAppServer.EnableAppRestrictions=true
JadeAppServer.AllowSchemaAndAppl="MySchema,SecretFixupApp" server=multiUser
host=devsrvr38 port=6015
```

Notes As the size of the command line is imposed by the operating system, this may restrict the number of JADE initialization file values that you can place on the command line. We recommend that JADE administrators keep the placement of initialization file parameters to a minimum, because long command lines can become hard to maintain. However, if you require only a few non-updating initialization file values, putting them on the command line saves the creation of a new JADE initialization file section.

You cannot use the **Application** class **setProfileString** or **setProfileStringAppServer** method to update JADE initialization file parameter values specified on the command line. (Attempts to do so return a value of **false** and the parameter values remain unchanged.)

If you specify JADE initialization file section and parameter names in the command line, initialization file parameter values that are normally updated by methods are *not* updated, as the command line values have precedence. The parameter values in the JADE initialization file remain unchanged in this situation. For example, if you specify **JadeServer.MaxServerThreads=10** in the command line of the JADE Remote Node Access program when the value of the [**JadeServer**] section **MaxServerThreads** parameter is **5** and you then change the **Maximum Server Threads** text box value in the Thread Configuration dialog to **7**, the command line value of the application remains **10** and the [**JadeServer**] section **MaxServerThreads** parameter remains **5**.

When obtaining values for command line arguments (for example, **path**, **schema**, **appServer**, and so on), the order of precedence is as follows.

1. Command line
2. If **name=unique-identifier** is on the command line, the [**unique-identifier.JadeCommandLine**] section parameter values are obtained from the JADE initialization file

3. The parameters from the [\[JadeCommandLine\]](#) section of the JADE initialization file
4. An internal default value, if applicable

See also "[Location of the JADE Initialization File](#)", "[Two-Level Section Names](#)" under "[Format of the JADE Initialization File](#)", in the *JADE Initialization File Reference*.

Handling Multiple Copies of the JADE Program

Use the **newcopy** command line parameter to force a new copy of the **jade.exe** JADE program to exist; for example, for testing in a multiuser environment. When this parameter is set to **true** (the default) and the JADE icon is clicked to launch JADE, a new copy of JADE is launched if the database is already open.

Specify a value of **false** to indicate that when the JADE icon is clicked and JADE is running, another application is started but another copy of the JADE program is *not* started; that is, execution is transferred to the copy of JADE that is currently running.

When initiating a thin client-based **jade.exe** executable with the **newcopy** command line parameter set to **false**, execution is transferred to an existing **jade.exe** copy if that copy is running in thin client mode and it is connected to the same application server (the TCP address and TCP/IP port number must match), so that only one copy of **jade.exe** runs multiple applications connected to the same application server.

If no other matching copy of **jade.exe** is running, execution continues as normal.

Note If you create a shortcut that has the **newcopy** parameter set to **false** and you specify a different JADE initialization file from the one with which the node was started, the active JADE initialization file is the one that was specified when the node started up and *not* the one specified in the **newcopy=false** shortcut. (You can call the [Application](#) class [getIniFileName](#) method in the new application to get the name of the initialization file that was used when the node started up.)

Specifying Your Administration Options

When you sign on to JADE, you can select the **Administration** option button from the Select Options group box to specify your installation preferences. The installation preferences are those that apply to all JADE browser and Painter windows in the JADE development database of your installed JADE release.

When JADE has been installed, these preferences can then be changed individually by a user (by selecting the **Preferences** command from the Options menu) or for the whole JADE development environment (by using this option).

The JADE installation preferences provide a form that enables you to select the appropriate sheet to specify the global options for your JADE development environment work sessions.

The options that you can maintain and the sections in this chapter (for options that apply only to the administrative JADE Installation Preferences dialog) or in Chapter 2 of the [JADE Development Environment User's Guide](#) that describe these options are listed in the following table.

Installation Option	For details, see...
Accelerator Keys	"Maintaining Accelerator Keys" , in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Browser	"Maintaining Browser Options" , in Chapter 2 of the <i>JADE Development Environment User's Guide</i>

Installation Option	For details, see...
Editor	" Maintaining the Editor Display ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Editor Key Bindings	" Maintaining Editor Key Bindings ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Editor Options	" Maintaining Editor Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Exit	" Maintaining Exit Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Lock	" Maintaining Lock Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Method	" Maintaining Method Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Miscellaneous	" Maintaining Miscellaneous Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Painter	" Maintaining Painter Options ", later in this chapter
Relationship	" Maintaining Relationship Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Schema	" Maintaining Schema Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Status list	" Maintaining Status List Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Text Templates	" Maintaining Text Templates ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>
Window	" Maintaining Window Options ", in Chapter 2 of the <i>JADE Development Environment User's Guide</i>

The JADE Installation Preferences dialog also contains the [File](#), [Admin](#), [Admin](#), and [Help](#) menus.

Using the File Menu

Use the commands in the File menu from the JADE Installation Preferences dialog to administer the installation preferences for your JADE development database.

The File menu commands are listed in the following table.

Command	For details, see...	Description
Save & Logoff	Saving Your Options and Logging Off	Saves your options, logs off from JADE, and displays the JADE sign-on dialog
Logoff	Logging Off from the Installation Preferences Dialog	Logs off from JADE and then displays the JADE sign-on dialog
Save & Exit	Saving Options and Exiting from the Installation Preferences Dialog	Saves your options and then exits from the JADE Installation Preferences dialog
Exit	Exiting from the Installation Preferences Dialog	Exits from the JADE Installation Preferences dialog

Saving Your Options and Logging Off

Use the **Save & Logoff** command from the **File** menu to save your installation preferences and then exit from the JADE Installation Preferences dialog, in preparation for starting a new work session.

» To save your installation preferences and then log off

- Select the **Save & Logoff** command from the File menu.

When all installation preferences have been saved, the JADE Installation Preferences dialog is closed after a momentary delay and the JADE sign-on dialog is then displayed, to enable you to enter your password and start a new JADE work session.

Logging Off from the Installation Preferences Dialog

Use the **Logoff** command from the **File** menu to exit from the JADE Installation Preferences dialog, in preparation for starting a new work session.

» To log off from the JADE Installation Preferences dialog

- Select the **Logoff** command from the File menu.

After a momentary delay, the JADE Installation Preferences dialog is closed and the JADE sign-on dialog is displayed, to enable you to enter your password and start a new JADE work session.

Note No installation preferences that you have specified will be saved.

Saving Options and Exiting from the Installation Preferences Dialog

Use the **Save & Exit** command from the **File** menu to save your installation preferences and then exit from the JADE Installation Preferences dialog.

» To save your installation preferences and then exit

- Select the **Save & Exit** command from the File menu.

When all installation preferences have been saved, the JADE Installation Preferences dialog is then closed after a momentary delay.

Exiting from the Installation Preferences Dialog

Use the **Exit** command from the **File** menu to exit from the JADE Installation Preferences dialog.

» To exit from the JADE Installation Preferences dialog

- Select the **Exit** command from the File menu.

After a momentary delay, the JADE Installation Preferences dialog is then closed.

Note No installation preferences that you have specified will be saved.

Using the Admin Menu

Use the commands in the Admin menu from the JADE Installation Preferences dialog to administer the installation preferences for your JADE development database.

The Admin menu commands are listed in the following table.

Command	For details, see...
Reset to Defaults	Resetting JADE Default Preferences
Remove Sources	Removing Source Code
Backup Database	Backing Up Your Development Database from a Client Workstation

Resetting JADE Default Preferences

Use the **Reset to Defaults** command from the Admin menu to reset all installation preferences to the default values.

Any installation preferences that you have specified are then reset to the JADE default preferences. These default values are the installation preferences that were last specified and saved using the JADE Installation Preferences dialog.

If you have not yet specified and saved any installation preferences, the default preferences are those that are supplied with JADE.

Removing Source Code

The **Remove Sources** command enables you to remove source code from your user-defined schemas only. You cannot remove source code from JADE-supplied schemas.

Use this command when you want to release JADE applications that do not contain method source code; for example, when you release a schema containing JADE applications developed for a third-party.

Notes Ensure that you have backed up the schema, including source code, before you use this command.

For details about including recompiled methods in patch versioning when a patch is to be applied to a schema that does not have source available, see "[Enabling or Disabling Patch Versioning](#)" and "[Setting Up a Patch Number](#)", in Chapter 3 of the *JADE Development Environment Administration Guide*. For details about finding the position in a method source if you want to locate the position at which an exception occurred in an application from which source code has been removed, see "[Finding a Method Source Position](#)", in Chapter 4 of the *JADE Development Environment User's Guide*. For details about encrypting extracted source code, see "[Encrypting Schema Source Files](#)", in Chapter 10 of the *JADE Development Environment User's Guide*.

Backing Up Your Development Database from a Client Workstation

The **Backup Database** command enables you to backup your JADE development environment database without having to sign off all users or bring down the server node.

You can backup your JADE development environment database online when the database is active for both read and write access. When backing up your JADE database, you can:

- Specify the backup directory path
- Compress or verify backed up files and optionally overwrite existing files
- Lock the database for write access

For more details, see "[Backing Up Your JADE Development Environment](#)", in Chapter 3 of the *JADE Database Administration Guide*.

Using the Patch Menu

Use the commands in the Patch menu from the JADE Installation Preferences dialog to administer patch version control for your JADE development database.

Patch version control enables you to set a numeric patch version that records all additions, deletions, and updates made to schema entities (for example, methods, properties, constants, and so on) until a new patch version number is set and the patch version history is removed when the changed entities in the previous patch version are extracted.

The Patch menu commands are listed in the following table.

Command	Documented under...	Description
Enable / Disable	Enabling or Disabling Patch Versioning	Enables or disables patch versioning for your database
Set Patch Number	Setting Up a Patch Number	Sets a new patch version number
Extract Patch	Extracting a Patch Version	Extracts all entities that have changed in the current patch version
Recreate History	Recreating a History of Patch Version Changes	Recreates the history of changes in the current patch version
Remove Patch History	Removing a Patch History of Changes	Removes the patch history that matched specified criteria

For details, see "[Patch Versioning](#)" under "[Administering Your JADE Environment](#)", in Chapter 3 of the *JADE Development Environment Administration Guide*.

Using the Help Menu

Use the commands in the Help menu from the JADE Installation Preferences dialog to access the standard Common User Access (CUA) help options. (For details about these options, see "[JADE Online Help](#)", in Chapter 2 of the *JADE Development Environment User's Guide*.)

The Help menu commands are listed in the following table.

Command	Description
Index	Opens the directory of JADE online help documents
About	Displays details about the current version of JADE

Specifying Your JADE Installation Preferences

The sheets of the JADE Installation Preferences dialog enable you to maintain your JADE installation preferences. The preferences that you specify apply to all new users.

The preferences for the current users are not modified. For details about maintaining preferences for current users and details about the sheets that are common to administrative installation and to individual user preferences, see "[Setting User Preferences](#)", in Chapter 2 of the *JADE Development Environment User's Guide*.


Specify your installation preferences when you first install JADE and before any users sign on, or at any time for new users of the JADE release.

The preferences that you set (and then save) become the new default preferences for your installation of JADE.

» **To maintain your installation preferences**

1. From the JADE sign-on dialog, select the **Administration** option button from the Select Options group box.

The JADE Installation Preferences dialog, shown in the following image, is then displayed.



The types of options are contained in sheets, with the **Editor** sheet displayed by default. (For details about using the **Editor** sheet, see ["Maintaining the Editor Display"](#) and ["Maintaining Editor Options"](#), in Chapter 2 of the *JADE Development Environment User's Guide*.)

2. Select the type of options that you want to change, by clicking on the sheet name; for example, click **Status List** if you want to view or change these options.
3. Make the required option changes.
4. To save your changes, use the **Save & Logoff** command or the **Save & Exit** command from the File menu. For details, see ["Saving Your Options and Logging Off"](#) or ["Saving Options and Exiting from the Installation Preferences Dialog"](#), respectively, earlier in this chapter.

When you have selected and saved your JADE preferences, the specified preferences become the new JADE default preferences when you exit or log off from the JADE Installation Preferences dialog.


Maintaining Painter Options

In JADE Painter, the default display of toolbars and grids and the position of the Properties dialog can be specified. For example, you can specify that the **Control** palette is not displayed on the Painter toolbar by default.

As painter values apply to the whole of the JADE development environment, the **Painter** sheet is available only on the administrative JADE Installation Preferences dialog.

» To change the default Painter options

1. Click the **Painter** sheet of the JADE Installation Preferences dialog. The **Painter** sheet, shown in the following image, is then displayed.



2. If you do not want the **Control** palette displayed in the Painter toolbar, check the **Hide Control Palette** check box.
3. If you do not want the **Alignment and Size** palette displayed in the Painter toolbar, check the **Hide Alignment/Size Palette** check box.
4. If you do not want the status bar displayed in Painter windows, check the **Hide Status Bar** check box.
5. If you do not want the **Tools** palette displayed in the Painter toolbar, check the **Hide Tools Palette** check box.
6. If you want controls on Painter forms to snap to a grid, check the **Snap to Grid** check box.

7. If you want a grid displayed on Painter forms, check the **Show Grid** check box.
8. If you do not want a default grid width of 10 pixels, enter the required width in the **Grid width** text box.
9. If you do not want a default grid height of 10 pixels, enter the required height in the **Grid height** text box.
10. If you want the Properties dialog to be always positioned on top of other control in Painter forms by default, check the **Properties On Top** check box.

Reregistering a JADE System in Batch Mode

The **jadregb** program enables you to automate the registration of a JADE system with your new licence information by running the registration program in batch mode (for example, from a command script), specifying the following information.

```
jadregb path=database-directory
       [online [ini=JADE-initialization-file-absolute-path-and-name]]
       [help | report | name="licence-name" key=licence-key
       [minStandard=integer-value] [minJade=integer-value]]
```

The number of server licences is split over the two types of run time operation; that is, standard (fat client) and JADE thin client.

Note JADE licenses are not transferred automatically between databases in an SDE. It is your responsibility to apply new licenses to any existing databases in an SDE. In addition, to ensure proper operation, you must apply the primary license to every secondary.

You can optionally specify the minimum number of licences reserved for both types of run time operation, if required. When you have successfully specified the new licence information for the database:

- Standard information is output to **stdout** and error information is output to **stderr**.

For details about displaying and redirecting the output from JADE batch utilities, see the [DisplayApplicationMessages](#), [LogServer](#), and [UseLogServer](#) parameters under "JADE Log Section [JadeLog]", in the *JADE Initialization File Reference*.

- The **_control.dat** file is updated.

If the **jadregb** executable program fails, a non-zero exit code is returned and an error message is displayed; for example, the licence key that you specified was invalid or you did not enclose your licence name in double quote characters (""). The batch registration program parameters are described in the following subsections.

path

The **path** parameter specifies the full path of the JADE database directory; for example:

```
c:\jade\system
```

ini

The optional **ini** parameter enables you to specify the fully qualified name of your JADE initialization file if it is not located in the database directory or it has a file name other than the default value of **jade.ini**.

name

The **name** parameter specifies your registered licence name (displayed on your Certificate of Authorisation, which may be an e-mail message providing you with your licence name and key). For example:

```
"Snazzy Solutions Incorporated"
```

You must specify your licence name, enclosed in double quote characters. This name must be typed correctly (it is case-sensitive), as it is validated against your licence key.

key

The **key** parameter specifies the assigned licence key; for example:

```
99999999FFFFFFFF99999999FFFFFFFF
```

Enter the licence key exactly as it is specified on your Certificate of Authorisation, but without spaces.

online

The optional **online** parameter specifies that the **jadregb** program attempts to sign on to the JADE Remote Node Access utility (**jadrap**) to update the licence key.

If you specify the **online** parameter, you may also need to specify the **ini** parameter, which consists of the full (absolute) path and name of the JADE initialization file that enables the **jadregb** program to obtain the multiuser initialization file settings that it requires to sign on to the JADE Remote Node Access utility (**jadrap**).

If you do not specify the **online** parameter, the **_control.dat** file is updated directly and no client application or database server can be running.

minStandard

The optional **minStandard** parameter specifies the minimum number of runtime standard fat client licences that can be reserved at run time to ensure that a specific number of licences is available for standard fat clients at any time; for example:

```
minStandard=4
```

You cannot specify a minimum number of standard fat client licences greater than the number of your registered server (run time) licences.

The default value of zero (**0**) indicates that there is no minimum number of standard fat client runtime licences.

minJade

The optional **minJade** parameter specifies the minimum number of runtime JADE thin client licences that can be reserved at run time to ensure that a specific number of licences is available for JADE thin clients at any time; for example:

```
minJade=6
```

You cannot specify a minimum number of JADE thin client licences greater than the number of your registered server (run time) licences.

The default value of zero (**0**) indicates that there is no minimum number of JADE thin client runtime licences.

report

The optional **report** parameter displays information about all existing licences installed in your system; for example, primary, secondary, and relational licences.

help

The optional **help** parameter displays the required parameters and their values.

Using the JADE Version Information Utility

The **jverinfo** JADE Version Information utility enables you to check the hot fixes that are applied to your JADE system and to optionally retrieve the version of user data map files. For more details, see the following subsections.

- [Checking which Hot Fixes are Applied](#)
- [Obtaining the Version Number of User Database Files](#)

The **jverinfo** program outputs the following version information to a file so that you can view it on your workstation monitor, print it out, or send it to JADE Support if requested to do so.

- System version information (for example, the operating system version, the CPU model, and the registered owner and organization of the software and hardware).
- File version information, starting with the installed location, full release version, and modified timestamp of each executable file followed by the installed location, full version number, and modified timestamp of each Dynamic Link Library (DLL) file.
- Types of CPU and operating system (for example, columns that contain **I686** or **AMD64** for the CPU type and **WinGUI**, **WinCE**, or **SYSV** for the operating system type).
- User data map file version number, starting with the installed location, version number, build type, architecture, and modified timestamp of each user data file.
- As well as listing the version details of executables and libraries found in the **bin** directory, **jverinfo** lists the version information of thin client download binaries if they are in the default download locations (that is, it will not find the download location using the values defined in the JADE initialization file).

If the directory does not exist or no executable or library files are found, nothing is output.

The following is an example subset of directories.

```
i686-msoft-win32-ansi\download\bin
i686-msoft-win32-unicode\download\bin
armv4i-msoft-wm60-unicode\download\bin
i686-msoft-x86emu-unicode\download\bin
```

The JADE Version Information utility program is not dependent on any other JADE libraries. You can therefore use one version of the **jverinfo** program to report on any release, whether it is a Unicode or an ANSI build.

To run the **jverinfo** program under a Windows operating system:

1. Copy the **jverinfo.exe** program to the JADE binary directory from which you want it run.
Alternatively, you can create a shortcut on your desktop or in the appropriate Start folder.
2. Execute the program to run it.

By default, the program writes its output to a file called **versioninfo.txt**, which is located in the working directory.

To automate the program, you can optionally specify the binary directory, user data map file directory (which is usually the system directory), system file directory, and the output file name, in the following format.

```
jverinfo [binpath=binary-directory-name] [binmask=binary-file-type]
         [datpath=user-data-directory] [datmask=user-data-file-type]
         [out=output-file-name|stdout] [syspath=system-file-directory]
         [sysmask=system-file-type] [noThinClients] [noExtraDirs] |
         [extraDirs=[path] [directory-name]]
```

The following is an example of the command line set up to run the program.

```
c:\jade\bin\jverinfo binpath=c:\jade\production_bin datpath=c:\jade\system
out=c:\jade\prodver.txt noExtraDirs
```

Note The **jverinfo** command line options are case-insensitive.

You can use the optional:

- **binpath** parameter to specify the binary directory that is to be scanned.
- **binmask** parameter to refine the files that are output using the **binpath** parameter. The default syntax of this parameter is ***.exe**.
- **out** parameter to specify **stdout** or the name of the output file that is created (defaulting to **versioninfo.txt**).
- **datpath** parameter to specify the user database map file directory (which is usually the **system** directory) that is to be scanned. It outputs an unformatted list of all user data map files, including the version number, the **ANSI**, **Unicode 16**, or **Unicode 32** build type, whether the architecture is **LittleEndian** or **BigEndian**, and the time and date that each file was last modified.
- **datmask** parameter to refine the user data files that are output using the **datpath** parameter. The default syntax of this parameter is ***.dat**.
- **syspath** parameter to specify the system file directory that is to be scanned and outputs the system file version, the **ANSI**, or **Unicode 16**, or **Unicode 32** build type, and whether the architecture is **LittleEndian** or **BigEndian**, and the time and date that each file was last modified.
- **sysmask** parameter to refine the system files that are output using the **syspath** parameter. The default syntax of this parameter is **_*.bin**.
- **noThinClients** parameter to disable the version details of thin client download binaries, if applicable.
- **extraDirs=*[path][directory-name]*** parameter to list custom (non-standard) directories to scan for binaries to display version information. The file specified by the **extraDirs** parameter must contain ANSI strings; wide-character strings are not supported by any version of **jverinfo**.

If you do not specify the optional **=*directory-name*** value, this parameter defaults to **jverinfo.extradir**. The **directory-name** value can be an absolute path or a relative path from the JADE Home directory (that is, one level up from the **bin** directory).

If the directory does not exist or it contains no ANSI files, it is ignored and nothing is output.

- **noExtraDirs** command line parameter, which you can use to disable the **extraDirs** functionality that lists version information on files in non-standard locations (that is, ignore the default **jverinfo.extradir** file, if it exists).

If the first character on an input line is the hash (**#**) character, the line is treated as a comment and is ignored.

The input line can be an absolute path or a relative path from the JADE Home directory (that is, one level up from the **bin** directory).

Checking which Hot Fixes are Applied

Should a problem arise that you cannot resolve by taking the appropriate action described in the relevant error message (documented in the [JADEMsgs.pdf](#) file) and your JADE licences include support, you may be asked for your current JADE version information in addition to the log files and user mode or process dumps specified in the previous section.

If you are uncertain of which hot fixes are applied to your JADE database, you can perform the following actions to determine exactly which hot fixes have been applied.

- Run the **jverinfo** JADE Version Information utility to obtain your current system and file versions. This stand-alone utility enables you to output your current JADE version information, the consolidated release you are running, and the hot-fixes with which you are running. Although you may think you have applied fixes, you may sometimes find that your records do not reflect the JADE system information itself.
- In the **RootSchema**, call the **Schema** class **getAppliedPatches** method to return a string containing all patches applied by a schema load to system schemas in your database. For details about the format of the string returned by this method, see the **getAppliedPatches** method in [Volume 2](#) of the *JADE Encyclopaedia of Classes*.

Obtaining the Version Number of User Database Files

If you want to obtain the version number of user database map files, you can run **jverinfo** JADE Version Information utility with the optional **datapath** parameter, to obtain the current user data map file version number. This parameter can be applied only to *user* database map files; that is, user schema files (for example, **_userdev.dat**, **_userscm.dat**, and so on) represented by the **DbFile** class **Kind_User_Schema** constant and user data files (for example, **_rootdef.dat**, **locktest.dat**, and so on) represented by the **DbFile** class **Kind_User_Data** constant.

Use the optional **setUserFileVersions** command in the **jdbutilb** batch JADE Database utility to set the user data map file version number to the specified 32-bit unsigned integer value.

When you specify the **datapath** parameter, the output file contains an unformatted list of all user data map files, including the version number, the **ANSI**, **Unicode 16**, or **Unicode 32** build type, whether the architecture is **LittleEndian** or **BigEndian**, and the time and date that each file was last modified.

In the following example of user data version information, **93** is the specified user data file version number. If a user data version number has not been specified, the version number is zero (**0**).

```
User:                               (path= c:\jade\system)
=====
locktest.dat                        93  Ansi,LittleEndian Tue Jun 10 08:16:21 2008
simpleconsumer.dat                  93  Ansi,LittleEndian Tue Jun 10 08:16:21 2008
simpleprovider.dat                  93  Ansi,LittleEndian Tue Jun 10 08:16:21 2008
wsconsumer.dat                     93  Ansi,LittleEndian Tue Jun 10 08:16:22 2008
_environ.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:20 2008
_monitor.dat                       93  Ansi,LittleEndian Tue Jun 10 04:00:57 2008
_reports.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:21 2008
_rootdef.dat                       93  Ansi,LittleEndian Tue Jun 10 04:00:57 2008
_stats.dat                         93  Ansi,LittleEndian Tue Jun 10 04:00:07 2008
_userdev.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:21 2008
_usergui.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:20 2008
_userint.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:20 2008
_userscm.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:20 2008
_userxrf.dat                       93  Ansi,LittleEndian Tue Jun 10 08:16:20 2008
```

In the **RootSchema**, call the **DbFile** class **getUserPatchVersion** method to return a 32-bit unsigned value as an **Integer64** primitive type, which is the unformatted version number of user data map files.

If a user data version number is not set, this method returns zero (**0**).

Using the JADE Sentinel Process Dumps Program

JADE Sentinel (**jadesentinel.exe**) monitors your active process. If, for any reason, a fault or problem occurs in this active process, JADE Sentinel takes a diagnostic copy in case the main process is unable to do so itself. No matter what happened to the process, JADE Sentinel ensures that you still get all of the information you need.

The **jadesentinel.exe** program is started by any JADE-built or supplied executable. It is a small executable that links to **jomos.dll**, in which all of the work occurs. It runs as a debugger attached to its parent process, looks for specific exceptions, performs out-of-process process dumps, and terminates the program, as appropriate.

The **jadesentinel.exe** is started automatically when the JADE-built executable starts. If it is necessary for you to start **jadesentinel.exe** manually, it has the following command line syntax.

```
jadesentinel.exe pid=pid ini=path\jade-initialization-name [prefix=executable-name]
```

The **pid** value specifies the process identifier of the process to monitor (that is, the parent process), the **ini** value specifies the path and name of the JADE initialization file, and the optional **prefix** value specifies the prefix to put on the dump file (for example, **jadrapp**, **jade**, **jadload**, and so on).

The **EnableSentinel** parameter in the [**FaultHandling**] section and the **ExcludeDiskCache** parameter in the [**JadeSentinel**] section of the JADE initialization file enable you to configure the **jadesentinel.exe** program.

Note You should set these values to **false** only when requested to do so by JADE Support.

This appendix covers the following topics.

- [Overview](#)
- [Enabling the Use of Generic Exit Values for Windows](#)
- [General Exit Values Unique to Each Program](#)

Overview

JADE provides exit values that apply to JADE programs and utilities. These exit values enable JADE administrators to develop tools that can take appropriate actions based on the exit values of the programs.

JADE programs can return exit values in the range of zero (**0**) through **2³²**. JADE programs generally returned zero (**0**) for success or the JADE error number if a problem occurs.

Standard exit values are limited to the range **0** through **127**. Any value above this range is reserved by the operating system. You can derive the signal number that caused the program to exit by subtracting 128 from the exit value; for example, an exit value of 139 indicates that the program exited because it received a fatal signal 11 (*SIGSEGV - Invalid memory reference*).

Using standard exit values, ranges of JADE error numbers are grouped into a common generic exit value. In addition, a range of exit values is set aside for warnings, enabling a program to return information without it being regarded as a fatal problem.

JADE programs or utilities default to using current exit values, or the generic exit values by setting an initialization file parameter. For details, see "[Enabling the Use of Generic Exit Values for Windows](#)", in the following section.

Note Using generic exit values does not impact on performance of your JADE programs or utilities. It gives the site administrator the ability to write standard support tools.

Enabling the Use of Generic Exit Values for Windows

The [\[FaultHandling\]](#) section of the JADE initialization file provides the [StandardExitValues](#) parameter that enables you to specify that JADE programs or utilities return generic exit values.

This parameter defaults to **false**, as JADE programs and utilities can return exit values in the range of zero (**0**) through **2³²** by default.

To specify that programs and utilities return generic exit values, set the [StandardExitValues](#) parameter in the [\[FaultHandling\]](#) section of the JADE initialization file to **true**.

In addition, you can use the:

- [CustomExitValue](#)<*JADE-error-message-number*> parameter in the [\[FaultHandling\]](#) section of the JADE initialization file when the [StandardExitValues](#) parameter is set to **true**, to remap JADE exit values (error numbers) to a user-defined standard exit code in the range 32 through 63.

The **CustomExitValue** parameter is valid only when the **StandardExitValues** parameter is set to **true**. If the **StandardExitValues** parameter is set to **false**, JADE exits with the applicable JADE error number. If the **StandardExitValues** parameter is set to **true**, JADE exists with the applicable error number from the remap table (listed in the following section) and checks for the existence of the **CustomExitValue** parameter or parameters in the [**FaultHandling**] section of the JADE initialization file.

- **Note** class **userExitCode** property to specify the value that is returned when a JADE program (for example, **jade.exe**, **jadapp**, **jadrap.exe**, **jaded**, and so on) exits. For more details, see [Chapter 1](#) of the *JADE Encyclopaedia of Classes*.

Tip You can use the **userExitCode** property, for example, to set a non-zero exit code that can then be checked in a batch file by using the **ERRORLEVEL** keyword to check for appropriate values of the **userExitCode** property.

General Exit Values Unique to Each Program

The following table lists the exit values that are unique to each program (that is, an exit value for the **jadload** program may have a different meaning from that for the **jade** program).

Value	Description	JADE Number Range
127	Fatal network errors	-101 through -120
0	Success, no error	0
1	Methods in error were detected by the schema load	8510
2	One or more commands in command file did not complete successfully	8514
3	Upgrade validation failed	8723
4	Reorganization is required	8511
5	Reorganization operation cancelled by user request	3404
6	Reorganization is suspended waiting for the transition to be initiated	3413
7	Versioned control subclasses require reorganization during online deployment	8525
8	Schema load resulted in one or more incomplete schemas	8527
9 through 31	Reserved, on an individual JADE program basis	Unspecified
32 through 63	User-defined exit values	Unspecified
64 through 78	Reserved by the operating system	Unspecified
105	JADE Object Manager errors	4 through 1299
106	Collection exception errors	1300 through 1349
107	Miscellaneous runtime errors	1400 through 1448
114	Trace exception errors	1500 through 1599
127	Remote procedure call (RPC) request errors	1600 through 1699
108	Security errors	1700 through 1799
113	Database engine errors	3000 through 3199

Value	Description	JADE Number Range
116	Synchronized Database Service (SDS) database errors	3200 through 3399
112	Database reorganization errors	3400 through 3499
127	Database server remote interface errors	3500 through 3599
120	JADE language interpreter errors	4000 through 4499
109	JADE Query Engine internal errors	4500 through 4999
114	File handling errors	5000 through 5099
114	Multimedia handling errors	5100 through 5299
114	Sort errors	5300 through 5399
121	Licence errors	5500 through 5599
112	JADE Object Manager data interchange errors	5700 through 5799
112	Internal management message exchange errors	5900 through 5999
119	Compiler errors	6000 through 6999
118	Method and schema file syntax errors	7000 through 7999
110	External database errors	8000 through 8255
125	ODBC errors	8256 through 8499
126	JADE Schema Load utility errors	8500 through 8599
111	Upgrade errors	8700 through 8799
124	JADE Database utility errors	9000 through 9999
117	TCP/IP network errors	10000 through 10499
122	JADE Monitor errors	11000 through 11999
127	JADE Remote Node Access utility errors	12000 through 12999
123	JADE user interface run time errors	14000 through 14499
123	JADE translatable string errors	14500 through 14999
114	Print errors	15000 through 15099
114	Editor errors	15500 through 15599
115	JADE development environment errors	16000 through 16999
117	Application connection errors	30000 through 30999
117	TCP/IP connection errors	31000 through 31499
117	Network proxy errors	31500 through 31999
117	Secure Sockets Layer (SSL) errors	32000 through 32499
117	X509 Certificate errors	32500 through 32999
112	Shared memory errors	33500 through 33599
116	Kernel, multiple server, errors, SDS	34000 through 34999
116	SDS and inter-node communication errors	35000 through 35999
64	Command line usage error	

Value	Description	JADE Number Range
65	Data format error	
66	Cannot open input	
67	Addressee unknown	
68	Host name unknown	
69	Service unavailable	
70	Internal software error	
71	System error (for example, cannot fork)	
72	Critical operating system file missing	
73	Cannot create (user) output file	
74	Input/output error	
75	Temporary failure; user is prompted to retry	
76	Remote error in protocol	
77	Permission denied	
78	Configuration error	